

# **Reference Data Management**

for SAP Master Data Governance

## **Functional Documentation**



---

## Content

1	Introduction to Reference Data Management	7
1.1	Usage and Main Components	7
1.2	RDG: Solution Components and Features	8
1.2.1	Data Model	8
1.2.2	Rule based Workflows	8
1.2.3	User Interfaces	9
1.2.4	Data Transfer for Initial Load	9
1.2.5	Data Replication and Local Staging Area	9
1.3	RDH: Solution Components and Features	10
1.3.1	Definition of Configuration Groups and Business Objects	10
1.3.2	Foreign Key Management	10
1.3.3	Field Reduction and Overwrite Protection	11
1.3.4	Controlled Replication and Activation	11
1.3.5	Monitoring and Logging	11
1.3.6	Customer defined Enhancements	11
2	Working with Reference Data Management, Governance	12
2.1	User Interfaces	12
2.1.1	RDM Launchpad	12
2.1.2	Creating a New Object	15
2.1.3	Creating Multiple Object Change Requests	18
2.1.4	Handling Change Requests	21
2.1.5	RDG Object & Change Request Overview	23
2.1.6	Changing an Already Existing Object	25
2.1.7	File Handling	26
2.1.7.1	File Download	27
2.1.7.2	File Upload	29
2.1.8	Full IT Governance Alternative - Local Staging Area	30
2.1.8.1	LSA – Administration	31
2.1.8.2	LSA – Maintain Local Staging Area	32

---

2.1.8.3	LSA – Creation of Snapshots	38
2.1.8.4	LSA – Snapshot Management	38
2.1.8.5	LSA – Solution Manager Integration	39
2.1.9	Business Governance Alternative – Direct Update	43
2.1.9.1	Activating Business Governance Alternative	43
2.1.9.2	Logging Business Governance Alternative	44
2.1.10	Foreign Key Check – Use Cases	48
2.1.10.1	Foreign Key Check for IT Alternative	48
2.1.10.2	Foreign Key Check for Business Alternative	49
2.1.10.3	Foreign Key Check for Reference Data Harmonization	49
2.1.11	Data Transfer	50
2.1.12	Deleting Objects	53
2.1.13	Exceptions	55
2.1.13.1	Product Hierarchy	55
2.1.13.2	Payment Terms	66
2.1.13.3	Exchange Rates	66
2.2	Roles and Authorizations	67
2.2.1	Display	67
2.2.2	Requester	67
2.2.3	Data Specialist	67
2.2.4	Data Steward	67
2.2.5	Local Staging Administrator	68
3	Working with Reference Data Management, Harmonization	69
3.1	The RDH Cockpit	70
3.2	Send Mode	71
3.2.1	Send Mode – Configuration Groups	71
3.2.2	Send Mode – Check Foreign Keys	73
3.2.3	Send Mode – Sending	74
3.2.3.1	Single Mode	75
3.2.3.2	Bundle Mode	76
3.2.3.3	Snapshot Mode	78
3.2.3.4	Transport Mode	79

---

3.2.3.5	Online Selection	82
3.2.4	Send Mode – Monitoring	85
3.3	Receive Mode	86
3.3.1	Receive Mode – Logging	87
3.3.2	Receive Mode – Activation	87
3.3.2.1	Compare	88
3.3.2.2	Delete	90
3.3.2.3	Save before Activate	90
3.3.2.4	Set Activation Flag	91
3.3.2.5	Activate	92
3.4	Expert Mode	93
3.4.1	Expert Mode – Business Objects	93
3.4.2	Expert Mode – Foreign Keys	94
3.4.3	Expert Mode – Recreate Foreign Keys	96
3.4.4	Expert Mode – Field Reduction	97
3.4.5	Expert Mode – Overwrite Protection	99
3.4.6	Expert Mode – Filter Groups	102
3.4.6.1	Testmode	103
3.4.6.2	Create Filter group	104
3.4.6.3	Activate Filter group	105
3.4.7	Expert Mode – Key Mapping	107
3.4.7.1	Customize Key Mapping	107
3.4.7.2	Maintain Key Mapping.	109
3.4.7.3	Show Key Mapping	110
3.4.7.4	Search Key Mapping	110
3.4.8	Expert Mode – Value Mapping	111
3.4.8.1	Create Value Mapping	111
3.4.9	Expert Mode – Enhancements	114
4	Reference Data Object Types (Content)	116
4.1	Content for Reference Data Harmonization (RDH)	116
4.2	Content for Reference Data Governance (RDG)	116
4.2.1	Financials	118

---

4.2.1.1	Account Group for General Ledger Accounts	118
4.2.1.2	Account Group for Vendors	118
4.2.1.3	Account Group for Customers	119
4.2.1.4	Business Area	120
4.2.1.5	Chart of Accounts	120
4.2.1.6	Company Code	121
4.2.1.7	Company ID	123
4.2.1.8	Controlling Area	124
4.2.1.9	Currency Code	127
4.2.1.10	Document Type	128
4.2.1.11	Exchange Rate	129
4.2.1.12	Functional Area	130
4.2.1.13	Operating Concern	131
4.2.1.14	Posting Period Variant	132
4.2.1.15	Tax Code	133
4.2.1.16	Valuation Class	135
4.2.2	Human Resources	135
4.2.2.1	Personnel Area	135
4.2.3	Logistics	136
4.2.3.1	BOM Usage	136
4.2.3.2	Division	137
4.2.3.3	Factory Calendar	138
4.2.3.4	Laboratory/Office	139
4.2.3.5	Location	140
4.2.3.6	Material Group	141
4.2.3.7	Material Status	142
4.2.3.8	Material Type	143
4.2.3.9	MRP Area	144
4.2.3.10	MRP Controller	145
4.2.3.11	MRP Profile	146
4.2.3.12	MRP Type	146
4.2.3.13	Plant	149
4.2.3.14	Storage Location	151
4.2.3.15	Unit of Measurement	152

---

4.2.3.16	Classification: CClass	153
4.2.4	Sales	156
4.2.4.1	Product Hierarchy	156
4.2.4.2	Sales Organization	157
4.2.4.3	Payment Terms	158
4.2.4.4	Distribution Channel	160
4.2.4.5	Incoterms	160
4.2.4.6	Sales Group	161
4.2.4.7	Shipping Conditions	161
4.2.4.8	Shipping Point	162
4.2.4.9	Shipping Type	163
4.2.5	Purchasing	164
4.2.5.1	Purchasing Group	164
4.2.5.2	Purchasing Organization	165
4.2.6	General Settings	166
4.2.6.1	Country	166
4.2.6.2	Region	167
4.2.6.3	Language Key	168
4.2.6.4	Public Holiday	168
4.2.6.5	Holiday Calendar	169

## 1 Introduction to Reference Data Management

Companies realized that the management of Reference Data (e.g. Country Code, Material Group, Unit of Measure, and many more) is as important as the management of Master Data (e.g. Business Partners, Materials or Financial Data). Without the central governance of Reference Data, a company that wants to be part of the digital world will not be successful.

Although Reference Data has a low frequency of changes, it has a high business impact as it is used in almost all business processes. Reference Data Management (RDM) for SAP MDG helps to address pain points and issues caused by non-harmonized, overlapping or unused Reference Data which lead to:

- Long and unreliable processes in Sales, Purchasing, Logistics and Finance
- Spoiled goods, inefficient storage and other commercial risks
- High project costs when IT systems need to be connected
- Wrong decisions because of reports that are based on low quality data

### 1.1 Usage and Main Components

Using Reference Data Management means establishing a single source of truth for Reference Data with maintenance processes driven by Data Stewards and Data Specialists. With this end users get fast, simplified and harmonized access to guided documentation based on reliable data and relevant metadata.

RDM consist of two components:

- Reference Data Governance (RDG)
- Reference Data Harmonization (RDH)

RDG is based on SAP Master Data Governance (MDG) which provides a framework with general functions for the maintenance of master data and reference data as well. It provides:

- Workflow driven maintenance processes based on "Change Requests"
- Data Transfer and Data Replication components including Monitoring
- Audit capabilities using "Change Documents"

RDH is used to consolidate and synchronize reference data based on SAP S/4 and provides:

- RDH Sender Cockpit (definition of reference data groups and replication)
- RDH Receiver Cockpit (controlled activation of reference data)

Both components are based on the Master Data Framework (MDF) with one sub-component described in this document (Local Staging Area) and other sub-components described in separate documents: "RDM Configuration" and "MDF Configuration Management".

---

## 1.2 RDG: Solution Components and Features

As an SAP MDG Add-On RDG reuses SAP MDG features and delivers content for Reference Data which includes:

- Data Model
- Rule Based Workflows
- Adjustable User Interfaces
- Data Transfer for Initial Load
- Data Replication and Local Staging Area

### 1.2.1 Data Model

RDM delivers the Data Model "I1" which defines the reference data objects and linkages between these objects. Data objects are defined based on technical entities which refer to other technical entities which might be part of the reference data object.

The data model can be extended as for other MDG applications based on the commonly used application framework provided by SAP.

The reference data catalog specifying all reference data objects which can be governed is provided in section 4.2 Content for Reference Data Governance.

### 1.2.2 Rule based Workflows

Maintenance processes in RDM are defined based on decision tables which define the configuration of the technical workflow. By reusing the Business Rule Framework (BRF) a flexible configuration and enhancement is provided which again is based on the framework delivered by SAP.

RDM delivers the following workflow template types for each object

- 3-step: Request, Process and Approve
- 2-step: Request and Approve
- 1-step: Create (Request and activation in the same step)




Figure 1: Change Request Types available in Itego RDM

Change Request Types are also delivered for data load (for File Upload and Data Import).

### 1.2.3 User Interfaces

User Interfaces in IRDM are developed based on Web Dynpro for ABAP and the Floorplan Manager (FPM). Adaptations of the user interface can be done on a configuration level ("Customizing") or on a development level reusing the enhancement concepts which are applied in every SAP MDG based application.

### 1.2.4 Data Transfer for Initial Load

RDM provides content which can be used by the "MDM Generic Extractor" (MDMGX) which is provided by SAP. With this capability reference data can be extracted as XML files from SAP systems and transferred to RDM. Another available option to load reference data into RDM is using a comma separated format (CSV) and the "File Upload" functionality of SAP MDG.

### 1.2.5 Data Replication and Local Staging Area

Data Replication from RDM can be based on any technical implementation. In the standard RDM supports SAP "Application Link Enabling" (ALE) by delivering content for "Intermediate Documents" (IDocs) which are connected to a "Local Staging Area" in the receiving system.

---

The “Local Staging Area” is delivered by Itego as a software component which receives messages from the SAP ALE framework and stores the contained reference data in data base tables. From there the reference data is transferred using the SAP Transport Management System.

## 1.3 RDH: Solution Components and Features

RDH delivers components which provide:

- Definition of Configuration Groups and Business Objects
- Foreign Key Management
- Field Reduction and Overwrite Protection
- Controlled Replication and Activation
- Monitoring and Logging
- Customer defined Enhancements

**Note:** RDH can be used without SAP MDG or RDG and helps to create consolidated reference data which can be synchronized without additional features for the controlled governance of reference data. With this it achieves to create good data quality in your reference data and provides an ideal basis for reference data governance project.

### 1.3.1 Definition of Configuration Groups and Business Objects

The usage Configuration Groups and Business Objects defines the scope of the Reference Data Harmonization. Using “Configuration Groups” all tables which should be harmonized can be grouped into one or many groups. Based on groups filters can be used to restrict the reference data values which should be in scope.

“Business Objects” help to define dependencies between configuration tables and with this create complete objects which can be harmonized as a complete object rather than a set of tables.

**Note:** Based on the generic Master Data Framework (MDF), RDH can harmonize and synchronize all SAP tables.

### 1.3.2 Foreign Key Management

Using Foreign Key Relations, RDH is able to automatically detect dependencies between tables and with this helps to define business objects and configuration groups.

---

### 1.3.3 Field Reduction and Overwrite Protection

The definition of the reference data harmonization scope does not stop with the usage or creation of configuration groups but can be optimized by the definition of globally and locally relevant fields (attributes of a table). In order to do this, field reductions for the data replication can be defined and an overwrite protection for receiver systems can be activated.

### 1.3.4 Controlled Replication and Activation

Based on filters within the configuration groups the controlled replication of reference data can be started. The system will only transfer the table entries which are within the defined filters and will follow the definition of globally relevant fields (attributes of a table). This can be started manually but is usually executed in the scheduled replications.

In the receiver system the user is enabled to control the activation of the new reference data provided. The data can be compared with data which is currently available in the receiving system and can be activated step by step. In doubt a snapshot of the current system configuration can be created, which enables the user to rebuild the configuration which existed before the activation. Note: In this case, new reference data needs to be deleted manually to avoid any side effects which could be caused by a local configuration.

### 1.3.5 Monitoring and Logging

RDH provide monitoring and logging features which enable the user to control the synchronization of reference data from the sender system to all receiving systems. Information about the filtering of tables and fields are provided in the sender. The monitoring of the technical interface is available in sender and receiver and activation logs are created in the receiving systems.

### 1.3.6 Customer defined Enhancements

Customer specific enhancements can be added using custom coding.

## 2 Working with Reference Data Management, Governance


Using RDM is very similar to the usage of SAP MDG for other domains like Financials, Materials or Business Partners. The general pattern of a launchpad leading to a search and the processing of the object does not deviate from the SAP standard behavior. Anyhow, as the content is aligned with the requirements of a reference data management application details might differ and are described in the sections below.

The chapter starts with an overview about the delivered user interfaces and concludes with the description of roles which can be assigned to the individual user.

### 2.1 User Interfaces

#### 2.1.1 RDM Launchpad

The launchpad of RDM contains shortcuts to every available RDM functionality in the MDG client. It can be accessed by executing transaction NWBC (NetWeaver Business Client) or /UI2/FLP (Fiori Launchpad) and using a standard or customized RDM role.



The drop-down menu on the left provides the same functionalities as the launchpad on the right. The guidance below will describe the access to all functionalities via the launchpad.

The launchpad itself is split into two sections and each is again split into several groups. The left part contains shortcuts to the single processing components (e.g. for Material Type, Currency, Division, ...). The right part contains shortcuts to general functionalities, such as change request monitoring, file up/download and manual data replication.

The important components on the right are:

### 2.1.2 “My Change Requests”: monitor the change requests you processed or submitted with your user (see section 2.1.3 Creating Multiple Object Change Requests

Implementing a multiple object change request allows users to manage and process changes for several related master data objects simultaneously within a single workflow transaction. This functionality is recommended for scenarios requiring the coordinated maintenance of interdependent entities (e.g., Company and the related Company Codes).

It is important to note that this specific configuration must be configured (see configuration guide).

Start the process by using this Fiori tile:




Select the configured change request type, enter a description and click 'Next'.


**Note:** if you are using it for the very first time you might need to use “Change Model” (blue link on the top next to “Save Draft”). Please select model “I1”.

 A screenshot of a Fiori configuration interface. At the top, there are two blue buttons: 'Save Draft' and 'Change Model'. Below is a horizontal navigation bar with five steps, each marked with a blue circle containing a number: 1. General Data, 2. Reason for Changes, 3. Changes, 4. Specify Target Systems, and 5. Check and Submit. Step 1 is highlighted with a thicker blue border. The main area is divided into 'Properties' and 'Control Data'. The 'Properties' section contains fields for 'Description' (with a red asterisk) and 'Type' (a dropdown menu showing 'Create ppv, ccode and company ID new try' and 'Z\_CCMULT', with 'Z\_CCMULT' currently selected). The 'Control Data' section contains fields for 'Due Date' (with a calendar icon), 'Priority' (a dropdown menu), and 'Reason' (a dropdown menu). A status message at the bottom of the properties section says 'Create ppv, ccode and company ID new try Z\_CCMULT'.

Enter a description and click 'Next'.



To specify the objects to be created/changed, select an entity type and click 'Specify Objects'.



Save Draft


1 General Data    2 Reason for Changes    3 Changes    4 Check and Submit

Objects to Be Changed

Specify Objects

Entity Type	Objects Specified
<input checked="" type="radio"/> Company	
<input type="radio"/> Company Code	
<input type="radio"/> Pstng period variant	

Enter new objects or select existing objects.



1 General Data    2 Reason for Changes    3 Changes    a Company    3 Changes    4 Check and Submit

Add Row  Delete Row(s)

Co.	Description
<input type="checkbox"/> C100	Company C100
<input type="checkbox"/> C101	Company C101


Click 'Copy Data'. Repeat for the other entity types. Click Next and submit your change request.

What would you like to do next?

[Create Another Change Request](#)

[Print the Change Request](#)

[Show My Change Requests](#)



Open your newly created change request (from "Inbox" or from "My Change Requests")

Name: IT\_ALL\_10 (Sabine)

**Change Requests**

Show:  From: 29.09.2025  To: 06.10.2025  Go | View: [Standard View]  Print Version

[Workflow Log](#) [Change Documents](#)

Change Request	Description	Status	Changed On	Changed By
<input type="radio"/> 14579	test sabine	To be Processed	06.10.2025	IT_ALL_10 (Sabine)
<input checked="" type="radio"/> 14586	create multiple objects: ...	To be Processed	06.10.2025	IT_ALL_10 (Sabine)

Read Only Print Preview Check Run Validation Validation Log Related Services

Change Request: 14586 Type: Create ppv, ccode and company ID new try Status: To be Processed

[Overview](#) [Changes](#) [Notes](#) [Attachments](#)

**General Data**

Processing: You are the processor of the change request

\* Description:  Due Date:

Priority:

Created On: 06.10.2025 13:31:54 Created By: IT\_ALL\_10 (Sabine)

Changed On: 06.10.2025 13:50:01 Changed By: IT\_ALL\_10 (Sabine)

Finalized On: Finalized By:

**Notes / Attachments**

Notes: 2 note(s) exist(s)

Attachments: 1 attachment(s) exist(s)

**Objects**


Entity Type	Number
Company	3
Company Code	2
Pstng period variant	2

Maintain your objects by clicking on the object link or navigating to "Changes". If click 'Edit' if needed. Repeat for all object types (entity types) that are listed in your change request.

After this click for example and "Finalize Processing" (this depends on the change request configuration). If needed, select "Run validation" and then click "Finalize Processing".

The next change request processor can approve the request which activates the objects and starts the data replication.

If the objects are maintained using the IT Governance alternative the objects can be processed in the Local Staging Area of the receiving system selecting the related change request (which bundles all changes and avoids the need to activate all of them separately).



- Handling Change Requests)

2.1.3 "Display Change Requests": display and (if you are authorized) process change requests (view section 2.1.4 Creating Multiple Object Change Requests

Implementing a multiple object change request allows users to manage and process changes for several related master data objects simultaneously within a single workflow transaction. This functionality is recommended for scenarios requiring the coordinated maintenance of interdependent entities (e.g., Company and the related Company Codes).


It is important to note that this specific configuration must be configured (see configuration guide).

Start the process by using this Fiori tile:



Select the configured change request type, enter a description and click 'Next'.

**Note:** if you are using it for the very first time you might need to use "Change Model" (blue link on the top next to "Save Draft"). Please select model "I1".




Save Draft   Change Model

1 General Data   2 Reason for Changes   3 Changes   4 Specify Target Systems   5 Check and Submit

<b>Properties</b>	<b>Control Data</b>
* Description: <input type="text"/>	Due Date: <input type="text"/>
* Type: <input type="text" value="Create ppv, ccode and company ID new try"/> <span>Z_CCMULT</span>	Priority: <input type="text"/>
Reason: <input type="text"/>	

Enter a description and click 'Next'.



1 General Data   2 Reason for Changes   3 Changes   4 Check and Submit

Explanation   Attachments

Create Company, Company Codes and Posting Period Variants

To specify the objects to be created/changed, select an entity type and click 'Specify Objects'.

Save Draft

1 2 3 **Changes** 4

General Data    Reason for Changes    Changes    Check and Submit

Objects to Be Changed

Specify Objects

Entity Type	Objects Specified
<input checked="" type="radio"/> Company	
<input type="radio"/> Company Code	
<input type="radio"/> Pstng period variant	

Enter new objects or select existing objects.

1 2 3 a 4

General Data    Reason for Changes    Changes    Company    Changes    Check and Submit

Add Row  Delete Row(s)

Co.	Description
<input type="checkbox"/> C100	Company C100
<input type="checkbox"/> C101	Company C101
<input type="checkbox"/>	
<input type="checkbox"/>	
<input type="checkbox"/>	

Click 'Copy Data'. Repeat for the other entity types. Click Next and submit your change request.

What would you like to do next?

[Create Another Change Request](#)

[Print the Change Request](#)

[Show My Change Requests](#)

All  1
 

Change request 14586 created

Open your newly created change request (from "Inbox" or from "My Change Requests")

Name: IT\_ALL\_10 (Sabine)

Change Requests

Show:  From:   To:   Go | View:

Change Request	Description	Status	Changed On	Changed By
<input type="radio"/> 14579	test sabine	To be Processed	06.10.2025	IT_ALL_10 (Sabine)
<input checked="" type="radio"/> 14586	create multiple objects: ...	To be Processed	06.10.2025	IT_ALL_10 (Sabine)
<input type="radio"/>				
<input type="radio"/>				
<input type="radio"/>				

Read Only Print Preview Check Run Validation Validation Log Related Services [?](#) [▼](#)

Change Request: 14586 Type: Create ppv, ccode and company ID new try Status: To be Processed

[Overview](#) [Changes](#) [Notes](#) [Attachments](#)

General Data

Processing: You are the processor of the change request

\* Description:  Due Date:

Priority:

Created On: 06.10.2025 13:31:54 Created By: IT\_ALL\_10 (Sabine)

Changed On: 06.10.2025 13:50:01 Changed By: IT\_ALL\_10 (Sabine)

Finalized On: Finalized By:

Notes / Attachments

Notes: 2 note(s) exist(s)

Attachments: 1 attachment(s) exist(s)

Objects


Entity Type	Number
Company	3
Company Code	2
Pstng period variant	2

Maintain your objects by clicking on the object link or navigating to "Changes". If click 'Edit' if needed. Repeat for all object types (entity types) that are listed in your change request.

After this click for example and "Finalize Processing" (this depends on the change request configuration). If needed, select "Run validation" and then click "Finalize Processing".

The next change request processor can approve the request which activates the objects and starts the data replication.

If the objects are maintained using the IT Governance alternative the objects can be processed in the Local Staging Area of the receiving system selecting the related change request (which bundles all changes and avoids the need to activate all of them separately).



- Handling Change Requests)
- “Display Change Documents”: display change documents
- “File Download”: execute a file download of selected object data (explained in section 2.1.9 File Handling)
- “File Upload”: execute a file upload of selected object data (explained in section 2.1.9 File Handling)
- “Replicate by Objects”: replicate an object to a connected system manually
- “Import Master Data”: import extracted object data from another system via an XML file

Details about the functionalities is provided the sections below.

The three  buttons on the upper right side of the screen allow for personalization, configuration and customizing of the page. You can also access the help center and quick help via them. The buttons are available on any page of the web application.

Please keep in mind that the launchpad can be replace by any other entry point like a collection of tiles in a customer specific portal or launchpad.

The Fiori Launchpad offers advanced features like creating a “My Home” page, searching for object types and advanced configuration and personalization options:

SAP Home ▾

Reference Data Governance ▾

### Financials

Change Requests and Documents

Change Requests Inbox	My Change Request	Display Change Requests	Display Change Documents
-----------------------	-------------------	-------------------------	--------------------------

### Objects

Business Area Search & Create	Chart Of Accounts Search & Create	Company Code Search & Create	Controlling Area Search & Create	Customer Account Group Search & Create	Document Type Search & Create	Exchange Rates Search & Create
Functional Area Search & Create	G/L Account Group Search & Create	Operating Concern Search & Create	Tax Code Search & Create	Valuation Class Search & Create	Vendor Account Group Search & Create	Currency Key Search & Create

### Processing of Multiple Objects

File Download	File Upload
---------------	-------------

SAP Home ▾

My Home Fiori Launchpad Reference Data Governance ▾ More ▾

Financials

Logistics

Sales and Distribution

Purchasing

Human Resources

General Settings

Classification

Objects

Division Search & Create	Factory Calendar Search & Create	Laboratory/Office Search & Create	Location Search & Create
Material Group Search & Create	Material Status Search & Create	Material Type Search & Create	MRP Controller Search & Create

## 2.1.4 Creating a New Object

For creating a new object, which is usually done by a requester (view section 1.2.2 – Rule Based Workflows), the user will usually open the launchpad. On the launchpad he chooses the object type he wants to create. This guide will show the process using the example of a Material Group.

After pressing “Material Group” on the launchpad, the object search of the object opens up:

Pend...	Material Gr...	Description (...)	Description (long te...)	Divis...	Valuati...	Unit of Measure	Approved By	Approved At	Rank
	01	Material group 1				U11		21.10.2020 09:29:06	100,00
	02	Material group 2				U11		21.10.2020 09:29:06	100,00
	MATGRP001	Mat Grp 001	Material Group 001			U11		21.10.2020 09:29:06	100,00
	MATGRP002	Mat Grp 002	Mat Grp 002-scy			U11		21.10.2020 09:29:06	100,00
	MATGRP004	Mat Grp 004 chg	Material Group 004 ...			U11		21.10.2020 09:29:06	100,00
	MATGRP003	Mat Grp 003	Material Group 003			U10		15.10.2020 08:47:11	100,00

The object search page is designed to identify and quickly find already existing objects. Before creating a new object, you should use the search function to verify if the object does not already exist.

To use the search function, you can use the input fields located below “Search Criteria”. Select an attribute on the left, select an operator and enter the value you wish to search for in the right field. You can also use the other lines to simultaneously define more search criteria. Once you are done, you can select, your “Maximum Number of Results”, and press “Search”. You will now get a list of all objects, which match your search criteria.


Other functions of the object search are:

- “Copy”: Create a new object, based on an already existing one

- “Mass Change”: Change several objects simultaneously (change request type to be configured)
- “Replicate”: Manually replicate an object to a connected system (which is usually done automatically after approval)
- “Replication Status”: Check the replication status of an object
- “Change Requests”: View change requests linked to an object

If the object that you want to create does not exist yet, you can press “New” or “Copy”, to initiate the creation process.

In the next popup (which may show different options, depending on your workflow configuration), the change request type selection is displayed (if more than one change request type is available for the specific user).



Each selection initiates a different change request type:

- “Create [...] and activate”: Instantly activates the object after creating it (1-step)
- “Create [...] with approval”: A data steward needs to approve the object creation before it is activated (2-step)
- “Create [...] with proc. and appr.”: A data specialist needs to check the created object and might enrich the data before the data steward is able to approve it (3-step)

Instructions on how to handle these different change request types can be found in section 2.1.4. For now, the next steps stay the same, no matter which change request type has been selected. The following window will show the “single object processing”:

Process Object with MDG

Side Panel

Save | Submit | Check | Undo | Redo | 

Change Request | Edit

General Notes Attachments

**General Data**

Change Request: 353  
 \* Description:   
 Priority:   
 Due Date:    
 Reason:

**Process Data**

Status: Changes to Be Executed  
 Current Workitem: New Change Request | What's Next  
 Created On/By: 23.10.2020 15:32:00 | Felix Back

**Audit Information**

Created On:   
 Changed On:   
 Approved On:       Created By:   
 Changed By:   
 Approved By:

**Material Group**

\* Material Group:   
 Description (short text):   
 Description (long text):       Division:   
 Valuation Class:   
 Default unit of weight:

**Material Group Descriptions**

Initially, you as the user need to provide information on the change request header - marked with "Change Request". You enter information such as a description (which is the only mandatory field in this case), priority and due date. In the "Notes" tab, you can provide a free text note, and in the "Attachments" tab, you can attach files and relevant links for the change request.

The "Audit Information" section is filled-out automatically, as it contains information about the time and date of the change request steps.

The "[Object]" section needs to be filled out with information about the object itself and depends on the customer specific configuration. It also varies from object to object. For some of them, you might also find one or more additional tab in the "[Object]" section (e.g. an address-tab), which needs to be filled out as well.

In the "[Object] Descriptions" section, you can add language dependent texts, which allow users with different logon languages to view the object description in their preferred language. Simply press "New", enter the language key(s), you want to use, and enter the according description (optional).

In the "Attachments" section, you can add metadata for the object itself – which allows to provide more details about the object itself. "Edit" and then either "File" or "Link".

After completing the request, you can press the "Check" button on the top left corner, to confirm that the data you entered is valid. You can then click "Submit", and your change request will be submitted. Depending on the selected change request type, the change request may need additional data and an approval. Please view the following section on "Handling Change Requests" for further instructions.

## 2.1.5 Creating Multiple Object Change Requests

Implementing a multiple object change request allows users to manage and process changes for several related master data objects simultaneously within a single workflow transaction. This functionality is recommended for scenarios requiring the coordinated maintenance of interdependent entities (e.g., Company and the related Company Codes).

It is important to note that this specific configuration must be configured (see configuration guide).

Start the process by using this Fiori tile:




Select the configured change request type, enter a description and click 'Next'.

**Note:** if you are using it for the very first time you might need to use "Change Model" (blue link on the top next to "Save Draft"). Please select model "I1".

 A screenshot of the Fiori tile interface. At the top, there are two buttons: 'Save Draft' and 'Change Model'. Below them is a horizontal navigation bar with five steps: 1. General Data (highlighted in blue), 2. Reason for Changes, 3. Changes, 4. Specify Target Systems, and 5. Check and Submit. The 'General Data' step is currently active. The main area is divided into 'Properties' and 'Control Data'. The 'Properties' section contains fields for 'Description' (a text input box) and 'Type' (a dropdown menu showing 'Create ppv, ccode and company ID new try' and 'Z\_CCMULT', with 'Z\_CCMULT' selected). The 'Control Data' section contains fields for 'Due Date' (a date picker), 'Priority' (a dropdown menu), and 'Reason' (a dropdown menu).

Enter a description and click 'Next'.




General Data    Reason for Changes    Changes    Check and Submit

Explanation    Attachments

Create Company, Company Codes and Posting Period Variants

To specify the objects to be created/changed, select an entity type and click 'Specify Objects'.



Save Draft


General Data    Reason for Changes    Changes    Check and Submit

Objects to Be Changed

Specify Objects

Entity Type	Objects Specified
<input checked="" type="radio"/> Company	
<input type="radio"/> Company Code	
<input type="radio"/> Pstng period variant	

Enter new objects or select existing objects.




General Data    Reason for Changes    Changes    Company    Changes    Check and Submit

Add Row    Delete Row(s)

Co.	Description
<input type="checkbox"/> C100	Company C100
<input type="checkbox"/> C101	Company C101

Click 'Copy Data'. Repeat for the other entity types. Click Next and submit your change request.



Open your newly created change request (from "Inbox" or from "My Change Requests")

Name: IT\_ALL\_10 (Sabine)

Change Requests

Change Request	Description	Status	Changed On	Changed By
14579	test sabine	To be Processed	06.10.2025	IT_ALL_10 (Sabine)
14586	create multiple objects: ...	To be Processed	06.10.2025	IT_ALL_10 (Sabine)

Read Only Print Preview Check **Run Validation** Validation Log Related Services ▾

Change Request: 14586 Type: Create ppv, ccode and company ID new try Status: To be Processed

**Overview** Changes Notes Attachments

General Data

Processing: You are the processor of the change request

\* Description:  Due Date:

Priority:

Created On: 06.10.2025 13:31:54 Created By: IT\_ALL\_10 (Sabine)

Changed On: 06.10.2025 13:50:01 Changed By: IT\_ALL\_10 (Sabine)

Finalized On: Finalized By:

Notes / Attachments

Notes: 2 note(s) exist(s)

Attachments: 1 attachment(s) exist(s)

**Objects**

Entity Type	Number
Company	3
Company Code	2
Pstng period variant	2


Save **Finalize Processing** Send for Revision Close

Maintain your objects by clicking on the object link or navigating to "Changes". If click 'Edit' if needed. Repeat for all object types (entity types) that are listed in your change request.

After this click for example and "Finalize Processing" (this depends on the change request configuration). If needed, select "Run validation" and then click "Finalize Processing".

The next change request processor can approve the request which activates the objects and starts the data replication.

If the objects are maintained using the IT Governance alternative the objects can be processed in the Local Staging Area of the receiving system selecting the related change request (which bundles all changes and avoids the need to activate all of them separately).



## 2.1.6 Handling Change Requests

Depending on your workflow configuration, some change requests need to be processed by users with special authorizations, such as data specialists and/or data stewards. If you are a user with these specific authorizations, you can follow this section for instructions on how to process change requests.

To access the change requests, which need to be processed by your user, press on "My Change Requests" under "Change Requests and Documents". You then will see a list of all change requests, which need to be processed by you or users which belong to the same role as you:

In the "Status" field, you can see that the change request still needs to be processed. In order to do this, press on the change request number. You will then get to the object overview page, where you can check the change request header and the data of the object, which is yet to be activated.

SAP®

Process Object with MDG

Save Finalize Processing Send for Revision Cancel Check Change Documents Workflow Log

Change Request

General Notes Attachments

**General Data**

Change Request ID: 7116  
Description: Demo Request 01  
Priority:  
Due Date:  
Reason:

**Process Data**

Status: To be Processed  
Current Workitem: Process Change Request 7116 (Demo Request 01)  
Created On/By: 29.10.2020 10:56:30 Felix Back  
Changed On/By: 29.10.2020 10:58:24 Felix Back

**Audit Information**

**Audit Information**

Created On: 29.10.2020 10:58:13  
Changed On:  
Approved On:

Created By: BACKF Felix Back  
Changed By:  
Approved By:

**Material Group**

Material Group: 00000999  
Description (short text): 00000999  
Description (long text): FB Material Group 999

Division:  
Valuation Class:  
Default unit of weight:

**Material Group Descriptions**

Depending on your role, you now have three options:


- Approve/Next step:** In order to simply approve the change request (or to send it to the next processor), you need to press the "Approve" or "Finalize Processing" button in the top left corner.
- Withdraw/Revise:** In order to withdraw or revise (send to previous processor) a change request, you have to press the "Withdraw" or "Send for Revision" button in the top left corner. To perform this step, you also need to provide a note in the change request header, explaining why you are performing this action.
- Next step with changes:** If you want to change the content of the change request, you can press on the "Edit" button in the "[Object]" section. The object fields are then open for input. After applying the changes, you can provide a note in the change request header, explaining your changes. You can then press "Approve" or "Finalize Processing" in the top left corner.

After performing one of the three actions above, the change request will either be released or sent (back) to the according processor, who is then able to perform similar steps.

### 2.1.7 RDG Object & Change Request Overview

Transaction /ITR/RDM\_Info provides an overview of all object values maintained within the RDG system as well as the associated Change Requests in which these objects have been processed. It is primarily intended for analysis and troubleshooting purposes, allowing users and developers to verify object data, trace processing history, and validate data consistency within the RDG environment.

To include recently activated Change Requests, select "JobStart" (1) and then "Refresh" (2). Otherwise, new Change Requests might not be included in the overview.



You can search for a specific object types (entities)




The column "Amount" shows the number of created objects for the entity. One entity can have several technical entities, for example for texts or addresses.

Choice

Entities   to

Entities selected : 00000056




Entity Type	Description	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	CR-Used
BKLAS_VAL	Valuation Class	BKLAS_VAL	17	BKLAS_VAL(TXT)	17					1
BLART	Document Type	BLART	62	BLART(TXT)	62					2
CHARHEAD	Characteristics	CHARHEAD	2	CHARHEAD(TXT)	2	CHARDESC	2	CHARREST	2	
CLASSHEAD	Classification	CLASSHEAD	2	CLASSHEAD(TXT)	2	CLASSCHAR	1	CLASSDESC	4	
COMPANY	Company Id	COMPANY	6	COMPANY(TXT)	6					7
COMPICODE	Company Code	COMPICODE	79	COMPICODE(TXT)	70	CC_ADRS	12			6
CURRENCY	Currency Key	CURRENCY	222	CURRENCY(TXT)	457					3
CUR_EXRA	Currency Exchange Rates	CUR_EXRA	13470							
DAYLIMIT	Payment Terms Details	DAYLIMIT	8	DAYLIMIT(TXT)	8					1
DISMM_ET1	MRP Type	DISMM_ET1	3	DISMM_ET1(TXT)	3					1
DISPO_ET1	MRP Controller	DISPO_ET1	2	DISPO_ET1(TXT)	2	PL_ADRS	5			1
DISPR	MRP profile	DISPR	4	DISPR(TXT)	4	DISPRFLD	236			4
EKGRP	Purchasing Group	EKGRP	3							4
EKORG	Purchasing Organization	EKORG	2							2

With show all CRs you get a list of Change Requests which have been executed




CR	CR-Type	CR-Text	Time Stamp	Date	Time	User Name	CR-Type-Description	Entity
15860	Z_CCMULT	PPV, Company, Com Code	20.251.202.170.619		00:00:00	IT_ALL_06	Create PPV, CC, Company with approval	COMPANY
15837	Z_CCMULT	PPV, Company, Com Code	20.251.202.083.752		00:00:00	IT_ALL_03	Create PPV, CC, Company with approval	COMPANY
15782	ILA1SL1	Country	20.251.130.065.601		00:00:00	IT_ALL_03	Load Country with approval	LAND1
15766	IP1TS01	Plant	20.251.127.141.205		00:00:00	IT_ALL_03	Create Plant	PLANT
15721	IVL1S02	Shipping Point	20.251.125.135.254		00:00:00	IT_ALL_06	Create Shipping Point	VSTEL_SP
15720	IVL1S01	Shipping Point	20.251.125.133.921		00:00:00	IT_ALL_10	Create Shipping Point	VSTEL_SP
15719	IVL1S02	Shipping Point	20.251.125.133.421		00:00:00	IT_ALL_10	Create Shipping Point	VSTEL_SP
15694	ICCIS01	Company Code	20.251.124.102.210		00:00:00	IT_ALL_10	Create Company Code	COMPICODE


Selecting the number from the "Amount" column for an entity opens an overview of all entries created and their creation details.



Entity Type	Description	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	CR-Used
BKLAS_VAL	Valuation Class	BKLAS_VAL	17	BKLAS_VAL(TXT)	17					1
BLART	Document Type	BLART	62	BLART(TXT)	62					2
CHARHEAD	Characteristics	CHARHEAD	2	CHARHEAD(TXT)	2	CHARDESC	2	CHARREST	2	
CLASSHEAD	Classification	CLASSHEAD	2	CLASSHEAD(TXT)	2	CLASSCHAR	1	CLASSDESC	4	
COMPANY	Company Id	COMPANY	6	COMPANY(TXT)	6					7
COMPICODE	Company Code	COMPICODE	79	COMPICODE(TXT)	70	CC_ADRS	12			6
CURRENCY	Currency Key	CURRENCY	222	CURRENCY(TXT)	457					3
CUR_EXRA	Currency Exchange Rates	CUR_EXRA	13470							
DAYLIMIT	Payment Terms Details	DAYLIMIT	8	DAYLIMIT(TXT)	8					1
DISMM_ET1	MRP Type	DISMM_ET1	3	DISMM_ET1(TXT)	3					1
DISPO_ET1	MRP Controller	DISPO_ET1	2	DISPO_ET1(TXT)	2	PL_ADRS	5			1
DISPR	MRP profile	DISPR	4	DISPR(TXT)	4	DISPRFLD	236			4
EKGRP	Purchasing Group	EKGRP	3							4
EKORG	Purchasing Organization	EKORG	2							2


ValCL	ARef	Obsolete	Created On	Created By	Changed On	Changed By	Appr.By U.	Approved At
0710	0003		27.04.2023 20:26:31	IT_ALL_03	12.11.2024 17:22:34	IT_ALL_05	IT_ALL_07	12.11.2024 17:22:34
0720	0001		27.04.2023 20:26:31	IT_ALL_03			IT_ALL_03	27.04.2023 22:26:36
1210	0002		27.04.2023 20:26:31	IT_ALL_03			IT_ALL_03	27.04.2023 22:26:36
3000	0001		27.04.2023 20:26:31	IT_ALL_03			IT_ALL_03	27.04.2023 22:26:36

The column "CR-Used" shows the number of Change Requests for this entity. When selecting it, more information about the change requests is shown, such as the Change Request ID, the user or which specific CR-Type was used.



Entity Type	Description	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	Entity Type	Amount	CR-Used
BKLAS_VAL	Valuation Class	BKLAS_VAL	17	BKLAS_VAL(TXT)	17					1
BLART	Document Type	BLART	62	BLART(TXT)	62					2
CHARHEAD	Characteristics	CHARHEAD	2	CHARHEAD(TXT)	2	CHARDESC	2	CHARREST	2	3
CLASSHEAD	Classification	CLASSHEAD	2	CLASSHEAD(TXT)	2	CLASSCHAR	1	CLASSDESC	4	4
COMPANY	Company Id	COMPANY	6	COMPANY(TXT)	6					7
COMPICODE	Company Code	COMPICODE	79	COMPICODE(TXT)	79	CC_ADDRS	12			6
CURRENCY	Currency Key	CURRENCY	222	CURRENCY(TXT)	457					3
CUR_EXRA	Currency Exchange Rates	CUR_EXRA	13470							3
DAYLIMIT	Payment Terms Details	DAYLIMIT	8	DAYLIMIT(TXT)	8					1
DISMM_ET1	MRP Type	DISMM_ET1	3	DISMM_ET1(TXT)	3					1
DISPO_ET1	MRP Controller	DISPO_ET1	2	DISPO_ET1(TXT)	2	PL_ADDRS	5			1
DISPR	MRP profile	DISPR	4	DISPR(TXT)	4	DISPRFLD	236			4
EKGGRP	Purchasing Group	EKGGRP	3							4
EKORG	Purchasing Organization	EKORG	2							2

By double-clicking on the CR-Type more details come up



CR	CR-Type	CR-Text	Time Stamp	User Name	CR-Type-Description	Entity	CR-Note	Keys
44	IVC1SL1	Loaded from IH2	20.240.118.113.522	HOEWLERD	Bewertungsklasse laden und aktivieren	BKLAS_VAL	VC01#7920#7900#3300#3200#3100#3050#3040	

## 2.1.8 Changing an Already Existing Object

Changing object data in RDM is similar to the create process described in section 2.1.4. Please refer to this before reading this section.

Starting on the launchpad, you need to navigate to the object, you want to change by clicking on the respective object type. You will get to the search result page of this object type. From there you can use the search function (explained in section 2.1.4) to locate the object that you want to change. Once you located the object, you can click on the link provided and will get to the object overview page. On this overview page, in the “[Object]” section, you have to click on “Edit”.

You may then have to select a change request type. For more details please refer to section 2.1.4. After selecting a change request type, the object data fields are open for input. You can now enter new or change current information. You can also add metadata, e.g. a file or a link which will provide more details about the object.

After adding or changing information, make sure that the change request header is filled out properly. Then press “Check” and/or “Submit”. Depending on the selected change request type, the change request may need approval.

## 2.1.9 File Handling

RDM offers the functionality of either importing or exporting object data via a file upload or download. These applications use a configurable file structure call "variant". This functionality allows for a convenient data transfer of larger amounts of data between two or more systems.

### 2.1.9.1 File Download

To initiate a file download, press "File Download" in section "Processing of Multiple Objects" on the launchpad. The following screen pops up:

File Download: Step 1 (Determine Entity Type)

Previous Next Execute Download Change Model Save Variant Delete Variant

1 Determine Entity Type 2 Define Selection 3 Define File Structure 4 Determine Download Settings 5 Check and Execute

**General Settings**

\* Entity Type:

\* Type of Transfer:  Attributes

\* Edition:

**Variant**

Variant:

For step one, select the Entity Type (Object) for which you want to download the data. For "Type of Transfer" select "Attributes". If provided, you could also use an existing variant. Press on "Next" and the step two pops up:

Previous Next Execute Download Save Variant Delete Variant


1 Determine Entity Type 2 Define Selection 3 Define File Structure 4 Determine Download Settings 5 Check and Execute

Download Active Data Only


**Selection**

Material Group:	<input type="text"/>	To:	<input type="text"/>
Asset Class:	<input type="text"/>	To:	<input type="text"/>
Approved By:	<input type="text"/>	To:	<input type="text"/>
Approved By:	<input type="text"/>	To:	<input type="text"/>
Valuation Class:	<input type="text"/>	To:	<input type="text"/>
Purch.value key:	<input type="text"/>	To:	<input type="text"/>
Unit of Measure:	<input type="text"/>	To:	<input type="text"/>
Division:	<input type="text"/>	To:	<input type="text"/>
Changed By:	<input type="text"/>	To:	<input type="text"/>
Created By:	<input type="text"/>	To:	<input type="text"/>

You can use the shown filter criteria to define which data objects will be downloaded. You can also choose if to download only active data which is usually advisable (as inactive data still needs approvals). Press on "Next" and step three will pop up:



If no variant has been created before you need to define a file structure. You can do this by adding the available attributes (on the left) to the Header or Data Row (on the right). It is advisable to save this file structure as a variant for later usage. Press "Next" and step four pops up:



You can select some options for the file that will be generated with the download. Press "Next" and step five will pop up and allows you to check your selection one more time. After verifying the selections, press "Execute Download" and save the generated file.

---

### 2.1.9.2 *File Upload*

Note: The file upload process is similar to the file download process. It is advised to read the file download section before reading this section. Also please keep in mind that you can use the file download to create file templates for a file upload.

If you get a file which contains data for objects that you want to upload you can initiate a file upload. On the launchpad, press on "File Upload" in section "Processing of Multiple Objects". A screen pops up, which is similar to the file download application.

In step one, you either need to select the object type or a variant which already contains the settings for this object type. Then press on "Next" and step two pops up.

In step two, you need to enter the file structure of the file if no variant is available. The file structure needs to match the file content. Then press on "Next" and step three pops up.

In step three you define upload settings, e.g. the upload mode, the execution of conversions and the separator. You also must select the file itself from one of your file directories - see "File Name". Then press "Next".

A pop up might ask you to select a change request type for the upload. Select it and press "OK". Step four pops up, where you can confirm your selections. Press "Execute Upload" to initiate the upload process which might create a change request which needs to be processed by other users.

### 2.1.10 Full IT Governance Alternative - Local Staging Area

Data can be replicated either using the “Business Controlled Governance Alternative” which will be described in the next chapter or using the “Full IT Governance Alternative”. The “Full IT Governance Alternative” involves a “Local Staging Area” (LSA) which is installed on receiving SAP business systems. The LSA serves the purpose to receive reference data objects from RDM and transfer it into the SAP configuration.

The diagram below shall provide an overview how the LSA is contributing to the flow of the reference data in the SAP system landscape.




Figure 2: Data Flow (SAP Systems)


After reference data is received by the LSA, it is stored in database tables (“Persistence”) until a “Subscriber” pulls the data and stores the data in a local SAP transport request which will be transported to the quality system, which belongs to the development system hosting the LSA. Eventually, the transport will reach the productive system, which starts the productive usage of the reference data included.

Note: the MDG system hosting the RDM application will also receive the reference data through SAP transport requests. As long as this transport did not reach the productive MDG system, other MDG applications like MDG for Material (which might be running on the same system) will not be aware of this data. The purpose of this behavior is the consistency of reference data across the complete system landscape. New reference data objects can only be used in the production system landscape after a consistent transport to all productive systems, including SAP MDG.

### 2.1.10.1 LSA – Administration

The administration cockpit (transaction /ITR/ADMIN\_STAGING) offers the user a well-structured system interface. Administrators have an overview of all processes (status of the Local Staging Area) and have the ability to react appropriately in certain cases.

Admin Staging Content



Records selected: 0075

Object	Objectname	LocalTable	TableName	StagTable	Hier.	LocalEntries	StagEntries	LocAddEnt
/ITR/B0007	RDM: Purchasing Org	T024E	Purchasing Organizations	/ITR/T024E	1	2	3	22
/ITR/B1072	RDM: Material Group	T023	Material Groups	/ITR/T023	1	2	3	
		T023T	Material Group Descriptions	/ITR/T023T	2	4	3	
/ITR/BT001	RDM: Company Code	T001	Company Codes	/ITR/T001	1	84	1	
/ITR/BT002	RDM: Language Keys	T002	Language Keys (Component BC-I18)	/ITR/T002	1	44	49	
		T002T	Language Key Texts	/ITR/T002T	2	1672	49	
/ITR/BT003	RDM: Document Types	T003	Document Types	/ITR/T003	1	53		
		T003T	Document Type Texts	/ITR/T003T	2	106		
/ITR/BT004	RDM: Chart of Acc.	T004	Directory of Charts of Accounts	/ITR/T004	1	33		
		T004T	Chart of Account Names	/ITR/T004T	2	77		
/ITR/BT005	RDM: Country	T005	Countries	/ITR/T005	1	253		
		T005T	Country Names	/ITR/T005T	2	708		
/ITR/BT006	RDM: Unit of Measure	T006	Units of Measurement	/ITR/T006	1	342		

On top of the page, you are able to provide search attributes and you will find shortcuts to other functionalities described in the following sections.

- **Start Local Staging Report:** To start a staging transport (See following section 2.1.6.2 LSA – Maintain Local Staging Area)
- **Show SnapShot:** Shows you the snapshot content. From there you can display the snapshots as well as restore configuration tables (See section 2.2.5 Local Staging Administrator). Important: Make sure that you are restoring the correct data (for more information read Section 2.1.6.5 LSA – Snapshot Management)
- **Create SnapShot:** Manual creation of a Snapshot (See Section 2.1.6.4 LSA – Creation of Snapshots)
- **Show Logs:** Displays the application logs (See Section 2.1.6.6 LSA – Logging)


In the section below ("Records Selected") you can choose the object types that you are looking for. You can also choose multiple objects types by clicking this  button.

The columns LocalEntries and LocalAdEntries (for addresses) show the entries in the configuration tables ("Customizing") of the local system, the columns StagingEntries and StagAdEntries show the staging content. Column ("StagEntries") shows the number of entries in LSA per object type. Another column ("StagTable") provides the technical name of the database tables provided by RDM which are the basis for the local staging area.

If you want to do a local change on the object, click on this  button, which you will find in the last column. It is usually only useful to do this when local attributes should be changed, that are not maintained in the RDM system but locally in the receiving system.

#### 2.1.10.2 LSA – Maintain Local Staging Area

Transaction "/ITR/STAGING (Maintain Local Staging Area)" or using the button in the administration cockpit allows access to the LSA as a "subscriber" and offers the following functionalities:



- Process Mode
  - o Enable local customizing: Create or use a transport and allow changes to local attributes. After changing the local attributes, you need to finalize the processing of the object by executing "Finalize local customizing".
  - o Global customizing only: Create or use a transport and release it without the opportunity to add local changes.
  - o Finalize local customizing: Merge local changes into the transport created or used by "Enable local customizing" and release the transport.
- Selection of objects and transport job
  - o Objects: Select the object types that you want to transfer into the configuration of the local system.

- Transport: Optional usage of an already existing transport. If not maintained the system will create a transport.
- Target System: The transport target specifies where a transport request is to be imported to. In the case of transport targets without specified target clients, the system administrator does not determine in which clients the client-dependent objects are to be imported until the time of import.
- Include local objects, allow deletion: Usually this is not selected which will allow a delta handling. Only the objects that have been currently changed or that have been newly added will be updated in the SAP configuration (See section 2.1.6.1 LSA - Delta Handling). If selected the complete content of the configuration tables will be added to the transport allowing local objects to be added and also allowing the local deletion of objects.
- Write protocol into logging: Enable Logging. (See section 2.1.6.4 LSA – Logging)
- Write snapshot: Create a snapshot of the configuration tables before executing the program (See section 2.1.6.2 LSA – Snapshot Management)

The "Processing Mode" is used to differentiate between two use cases:

- Local Customizing
  - Reference Data created or changed on RDM can be enriched by the maintenance of local attributes
- Global Customizing
  - Reference Data created on RDM is transferred without additional changes into an SAP transport

In both use cases, a transport can either be created or reused. The reuse of transport offers more flexibility which can be used to

- Add additional changes (independent of RDM) to the transport
- Reuse transports that have been created in an earlier step of the process (e.g. as a result of a Change Request created in the SAP Solution Manager)

Prerequisite for reusing a transport: User of transaction "/ITR/STAGING" is assigned to the transport.

**Note:**

For the maintenance of the Factory Calendar the system creates a transport of type "Work-bench". If a transport should be reused, please make sure that this type is used as well.

For the use case "Local Customizing" the subscriber needs to "Enable local customizing" which means that the reference data objects are transferred to the SAP configuration tables and can

be enriched using transaction "SPRO" (Customizing). After this has been done, the subscriber needs to "Finalize local customizing" which concludes the maintenance for the objects which are in the scope of the subscription.

The scope of the subscription is defined by the "Objects" defined in the "Selection of objects and transports". The set of objects can either hold one or many reference data object types available in RDM.

Subscriptions can also be automated by scheduling variants of report /ITR/ST\_TRANS\_CREATE (which is the report linked to transaction /ITR/STAGING").

#### 2.1.10.2.1 LSA – Delta Handling

The delta handling feature of the LSA is activated by a checkbox, which determines whether the staging transport should contain every available object or only the objects that have been changed since the staging report was last executed.

The modes "Enable Local Customizing" and "Finalize Local Customizing" do **not** allow the user to use the delta handling method. When you select the mode "Global customizing only", the delta handling method is enabled by default.

Note: If the Checkbox "Incl. local obj.,allow deletion" is **not** selected, only the objects that have been currently changed or that have been newly added will be sent to SAP configuration! If the option is marked the LSA transfers all entries in the configuration table of the specified object.


Incl. local obj.,allow deletion




*Example: If table T001 (Company Codes) consist of 500 entries and through RDM there is one more entry, either 501 entries or only 1 entry is transferred to the transport which is created by executing "Maintain Local Staging Area".*

It could still be useful to transport all data. In this case, the SAP configuration that receives this transport will have a complete update.

*Example: If entries are deleted in this way, they would subsequently have to be deleted manually in the MDG as well. This is only a special case, but it shows that sending all data also has its advantages. Therefore, the two options are available.*



With Delta Handling



#### 2.1.10.2.2 LSA – Logging

The logging functionality helps to monitor the LSA functionality in more detail and allows to resolve problems that might occur in the maintenance processes. The transaction "/ITR/STAGING" is required to execute this function. Clicking on "Show Logs" opens the following window.

Display Application Logs (RDM-Staging-Report)

Menu	Save as Variant...	Back	Exit	Cancel	System	Execute	Program Documentation						
<b>Time Restriction</b> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="width: 20%;">Maximum Number of Logs</td> <td style="width: 80%; text-align: right;">[ ]</td> </tr> <tr> <td>From (Date/Time)</td> <td style="text-align: right;">08.03.2021 00:00:00</td> </tr> <tr> <td>To (Date/Time)</td> <td style="text-align: right;">08.03.2021 23:59:59</td> </tr> </table>								Maximum Number of Logs	[ ]	From (Date/Time)	08.03.2021 00:00:00	To (Date/Time)	08.03.2021 23:59:59
Maximum Number of Logs	[ ]												
From (Date/Time)	08.03.2021 00:00:00												
To (Date/Time)	08.03.2021 23:59:59												
<b>Logs Produced By</b> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="width: 20%;">User</td> <td style="width: 20%; text-align: right;">[ ]</td> <td style="width: 20%; text-align: center;">to</td> <td style="width: 20%; text-align: right;">[ ]</td> <td style="width: 10%; text-align: right;">[ ]</td> </tr> </table>								User	[ ]	to	[ ]	[ ]	
User	[ ]	to	[ ]	[ ]									
<b>Logs in Editing</b> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="width: 50%; text-align: left;"> <input checked="" type="radio"/> Display header data only  <input type="radio"/> Do not display         </td> <td style="width: 50%; text-align: left;"> <input type="radio"/> Display all (not recommended, see documentation)  <input type="radio"/> Wait for end of editing         </td> </tr> </table>								<input checked="" type="radio"/> Display header data only <input type="radio"/> Do not display	<input type="radio"/> Display all (not recommended, see documentation) <input type="radio"/> Wait for end of editing				
<input checked="" type="radio"/> Display header data only <input type="radio"/> Do not display	<input type="radio"/> Display all (not recommended, see documentation) <input type="radio"/> Wait for end of editing												
<b>Display</b> <table style="width: 100%; border-collapse: collapse;"> <tr> <td style="width: 50%; text-align: left;"> <input checked="" type="radio"/> ALV Grid Control  <input type="radio"/> Text Format         </td> </tr> </table>								<input checked="" type="radio"/> ALV Grid Control <input type="radio"/> Text Format					
<input checked="" type="radio"/> ALV Grid Control <input type="radio"/> Text Format													


- **“Logs in editing”:** Besides the log produced by earlier runs, you even have the possibility to take a detailed look at the logs that are written for runs that are currently in execution. If problems occur, you can adjust the level. You have the following options when deciding how the report should handle these logs:
  - “Display header data only”: The report shows only the header data and no messages.
  - “Do not display”: The report does not show the header data or messages.
  - “Display complete log”: The report shows the header data and messages. This can, however, lead to the problems discussed above.
  - “Wait for the completion of editing”: The report waits until all relevant logs are written.
- **“Display”:** You can choose to display the logs using an ALV Grid Control or in text format. As well as the format, there are slight differences in the functions available with each option:
  - ALV: You can display the long texts for individual messages and the technical details of logs and messages by choosing the corresponding ALV functions.
  - Text: All logs, including messages and context information, are displayed at once. You can therefore use the text search function to search for a particular text in all messages, for example.

Note: If you display the report in text format, the selected selection criteria are also displayed.

### 2.1.10.3 LSA – Creation of Snapshots

Snapshots store the entries of the configuration table in different versions. Snapshots can be created manually or automatically. Manually by executing a report which creates a new version or automatically through the Local Staging Area or the inbound process for a generic IDoc. This allows you to restore data to a former state that you consider good.


For example, if you want to transport a new object or an object that has been changed recently, a snapshot will be created automatically if the checkbox “write snapshots” is selected. This checkbox should be selected by default.



### 2.1.10.4 LSA – Snapshot Management


The snapshot management ensures that changed configuration tables can be recreated based on a consistent version of this table.

Clicking the button  will open the following page.



Select the table from which the non-consistent data should be restored (e.g. table T001 (company code). Select the object you want to restore (Right-click → restore).

To ensure that you are restoring the correct data, check the entries in the table. If it is an address object, the AD-Entries column can be helpful to make sure that the address is correct.




CoCode	Company Name	City	Ctr	Crcy	Language	ChAc	Max.ex dev	FV	C	Company Address	VAT Registration No.	FMA
0001	SAP A.G.	Walldorf	DE	EUR	DE	INT	10	K4	2			
	(S-HT-1W)	Palo Alto	US	USD	EN	INT	10	K4	1			
	Erbank Deutschl.	Walldorf	DE	EUR	DE	0MB1		K4	1			
	Template AE	Dubai	AE	AED	EN	INT		K4	1	22231		
	Template AR	Argentinien	AR	ARS	ES	INT		K4				
	Template AR	Argentinien	AR	ARS	ES	INT	10	K4				
	Template AT	Austria	AT	EUR	DE	INT	10	K4	2			
	Template AU	Australia	AU	AUD	EN	INT	10	V6				
	Template BE	Belgium	BE	EUR	EN	CABE	10	K4	2		BE000009797	
	Template BR	Brazil	BR	BRL	PT	INT	10	K4				
	Template CA	Canada	CA	CAD	EN	CANA	10	K4	2			

Note: Not every role has the authorization to restore a snapshot. (See section 2.2.5 Local Staging Administrator)

#### 2.1.10.5 LSA – Solution Manager Integration

In order to integrate the transport which is created from the Local Staging Area into Solution Manager ChaRM Tickets, choose the appropriate option from the Local Staging Area cockpit.



Admin Staging Content												
Choice		Records selected: 0088										
Object	ObjectName	LocalTable	TableName	StagTable	Hier.	LocalEntries	StagEntries	LocAddEnt	StagAddEnt	Cust		
/ITR/B0007	RDM: Purchasing Org	T024E	Purchasing Organizations	/ITR/T024E	1	60	1					
/ITR/B1072	RDM: Material Group	T023	Material Groups	/ITR/T023	1	76	142					
		T023T	Material Group Descriptions	/ITR/T023T	2	163	2					
/ITR/RT001	RDM: Company Code	T001	Company Codes	/ITR/T001	1	144	1	90	50			
		T002	Language Keys (Component BC-I18)	/ITR/T002	1	54						
		T002T	Language Key Texts	/ITR/T002T	2	1623						
		T003	Document Types	/ITR/T003	1	61	64					
		T003T	Document Type Texts	/ITR/T003T	2	100	9					
		T004	Directory of Charts of Accounts	/ITR/T004	1	56						
		T004T	Chart of Account Names	/ITR/T004T	2	99						
		T005	Countries	/ITR/T005	1	267						
		T005T	Country Names	/ITR/T005T	2	719						
/ITR/BT006	RDM: Unit of Measure	T006	Units of Measurement	/ITR/T006	1	275	13					
		T006A	Assign Internal to Language-Dependent Unit	/ITR/T006A	2	552	18					

Select checkbox "SolMan: Create Ticket" and select the appropriate configuration ID for the Solution Manager which is connected to your Local Staging Area.

Maintain Local Staging Area

StagContent Show Logs Show SnapShots

Process mode

Enable local customizing  
 Global customizing only  
 Finalize local customizing

Selection of objects and transport job

Objects: /ITR/B0007

Transport job: ITR/B0007

Target system: SolMan-ConfigID: SOLMANDEMO to: [ ]

Incl. local obj.,allow deletion:

write protocol into logging:

write snapshots:

Standard-Transport-Text:

SolMan: Create Ticket:

The process will create a ChaRM ticket and will log this action:

```
data Entry: 400Z001
00060 AFTER: Entries in CustomizingTable T024E found
Transport ITRK906050 successful created
Task ITRK906051 successful created
SolMan-Ticket created: 8000002600
```

After this the responsible users can access the ticket in the SAP Solution Manager and process the ticket according to the testing status. RDM creates an attachment with additional information about the data included based on the logging information in the Local Staging Area. Please check the example below.

Search: Standard Changes

Document Type: Is Standard Change  
 Document ID: contains  
 Free Text: contains  
 Description: contains  
 Time Frame: Is Today

Maximum Number of Results: 100

Search | Clear | Save Search As: | Include View | Save

Result List: 3 Standard Changes Found

Change ID	Description	Priority	Status	Create...	Category	Relate...	Reque...	Reque...
8000002596	Test	4: Low	In De...	07.10....			07.10....	10.10...
8000002598	RDM: 2. Test	2: High	In De...	07.10....			07.10....	21.10...
8000002600	RDM Reference Data - Purchasing Org	2: High	Created	07.10....			07.10....	14.10...

Search for ChaRM ticket which has been created.

Save | Display | Cancel | Edit | Create Follow-Up | Actions | Send E-Mail | Print Preview | Print | Display Object Relationships

Status Overview

1 Created | 2 In Development | 3 To Be Tested | 4 Successfully Tested | 5 Imported into Production | 6 Withdrawn

Details | Edit

General Data

ID:	8000002668
Description:	RDM: Material Group - T023, T023T
Developer:	Mr. SAP Backoffice
Tester:	
IT Operator:	
Change Manager:	Mr. SAP Consulting
Current Processor:	

Implementation Data

Change Cycle / Phase:	ITEGO Continous cycle
Type / ID:	Continual Cycle
Landscape / Branch:	ITEGO Solution RDM
Development Close:	
Go-Live Date:	

Project Planning

Project Name:	<None>
---------------	--------


Attachments

Actions	Name	Type
Properties	RDM - Local Staging Area Logging	Simple Text

Processing of the ticket

```
Start: 2022-10-27T12:47:25
-----
Logging started
Delta-Mode selected
Processing started for Object: /ITR/B1072 table: T023
Processing started for Object: /ITR/B1072 table: T023T
Snapshot created with index(es): RDM-T023-124725 table: T023
00023 BEFORE: Entries in CustomizingTable T023 found
Staging entries for /ITR/T023 found 00001
Insert entries for T023 found 00001
Update entries for T023 found 00000
Insert entries for /ITR/T023 processed: 00001
data Entry: 20009
00024 AFTER: Entries in CustomizingTable T023 found
Snapshot created with index(es): RDM-T023T-124726 table: T023T
00028 BEFORE: Entries in CustomizingTable T023T found
Staging entries for /ITR/T023T found 00002
Insert entries for T023T found 00002
Update entries for T023T found 00000
Insert entries for /ITR/T023T processed: 00002
data Entry: 200D09
data Entry: 200E09
00030 AFTER: Entries in CustomizingTable T023T found
Transport IR1K900451 successful created
Task IR1K900452 successful created
Transport IR1K900451 could not be released
-----
End: 2022-10-27T12:47:25
```

Additional information attached to the ticket based on the LSA logging



Example: Necessary process steps for finalizing the Import to productive systems.


## 2.1.11 Business Governance Alternative – Direct Update

Besides the possibility to replicate data via the “Full IT Governance Alternative”, data can also be replicated without the need to create transports using the LSA (Local Staging Area). This alternative is called “Business Controlled Governance Alternative” and is using the “Controlled Direct Update”.

Just like replicating Master Data, the data will be replicated directly to the productive receiver systems. This avoids additional IT processes which are used to promote the reference data from the development system to the test system and later to the production. The governance is controlled completely by the business users, using the workflow processes within RDM.


### 2.1.11.1 Activating Business Governance Alternative

For the activation use the RDMIMG (transaction /ITR/RDMIMG) and click “Configure Business Alternative”.



In the “Activate Direct Table Update” the entity with its Business and Logical system (Receiver systems) for which the Direct Update needs to be activated, must be added. The checkbox indicates the replication via direct update. If the direct update is inactive, the objects will be replicated using the “Full IT Governance Alternative”, involving the Local Staging Area.

**SAP Change View "RDM: Activate Direct Table Update": Overview**



The screenshot shows a SAP interface titled 'RDM: Activate Direct Table Update'. The table has columns: Business System, Logical system, Entity Type, and Activation status (A). The data includes:

Business System	Logical system	Entity Type	A
IH2400	IH2400	PAYMNTTRM	<input checked="" type="checkbox"/>
IH2400	IH2400	PLANT	<input checked="" type="checkbox"/>
IR1200	IR1200	MATKL	<input checked="" type="checkbox"/>
IT9400	IT9400	BKLAS_VAL	<input checked="" type="checkbox"/>
IT9400	IT9400	BLART	<input checked="" type="checkbox"/>
IT9400	IT9400	COMP CODE	<input checked="" type="checkbox"/>
IT9400	IT9400	CURRENCY	<input checked="" type="checkbox"/>
IT9400	IT9400	CUR_EXRA	<input checked="" type="checkbox"/>
IT9400	IT9400	DAYLIMIT	<input checked="" type="checkbox"/>

If a reference data object includes more than one entity type, the direct update must be activated for both entity types to work correctly. An example for that would be "Terms of Payment". Here the entity types PAYMNTTRM and DAYLIMIT are used to implement the "Terms of Payment" using table T052. Both objects need the activation of the direct update.

	MANDT	USMD_ENTITY	SERV_IMPL	LSA_TAB_POS	LSA_TABLENAME
<input type="checkbox"/>	100	DAYLIMIT	/ITR/PAYMD	1	/ITR/T052
<input type="checkbox"/>	100	PAYMNTTRM	/ITR/PAYMN	1	/ITR/T052

### 2.1.11.2 Logging Business Governance Alternative

In order to check if the data has been sent to the receiver system, the logs can be displayed and checked. First, the log in the receiver system must be checked using transaction DRFLOG.

In the example below the object type created was "Storage Location" (LGORT). The messages show that the data has been replicated successfully.

**SAP Display Logs for Replication Model -**

Technical Information

Date/Time/Replication Model/Business Object Type	Numb.	Replication Mod...	Business Object Description	Outbound Im...
> 09.05.2023 14:56:31 RDM	I_DIS 27	Reference Data ...	MRP Controller	/ITR/DISPO
> 09.05.2023 15:37:42 RDM	I_DIS 27	Reference Data ...	MRP Controller	/ITR/DISPO
09.05.2023 08:10:10 RDM	I_LG(17)	Reference Data ...	RDM: Storage Location	/ITR/LGORT
> Process outbound implementation RDM – O 17				
09.05.2023 09:15:25 RDM	I_LG(22)	Reference Data ...	RDM: Storage Location	/ITR/LGORT
>	5			

Message Text

- DirectTableUpdate->System: ID1400
- DirectTableUpdate->Table: T001L
- DirectTableUpdate->Key: 1000001LOC1
- Process outbound implementation RDM – Outbound Implementation for LGORT (StorageLo (/ITR/LGORT)
- More Messages During Output Processing
- Replication to business system ID1400
- Filter object /ITR/LGORT – RDM – Filter for LGORT (SLOC): end result of filtering 1
- Process Messages
- CREQUEST: 000000001167 Test DU StoLoc 09.05.2023 11:14:53 SATTLERU
- IDoc 0000000000046017 with a data record was transferred
- GenericIdoc sent for: /ITR/T001L with 1 record(s)
- Processing of outbound implementation /ITR/LGORT completed
- More Messages During Output Processing

The logging can also be checked in the receiver systems if it has been activated. To activate it in the receiver systems, execute transaction SM30 and maintain table /ITR/CUST\_CODE as shown below.


**SAP Data Browser: Initial Screen**

Table Name: /ITR/CUST\_CODE

Add the function module /ITR/RDH\_LOGGING\_RECEIVER\_SIDE and /ITR/RDM\_FOREIGN\_KEY\_CHECK and activate it.


## Data Browser: Table /ITR/CUST\_CODE Select Entries

92



MANDT	TABLENAME	EVENTID	EVENT_POSITION	FUNCNAME	ACTIVE
100	*	1	000001	/ITR/RDH_LOGGING_RECEIVER_SIDE	X
100	*	5	000002	/ITR/RDM_FOREIGN_KEY_CHECK	X

The logging can be analyzed with the transaction SLG1. Enter the Subobject /ITR/CUSTSYNC.



Object: /ITR/ RDM-StagingLogs  
 Subobject: /ITR/CUSTSYNC  
 External ID:

Time Restriction  
 From (Date/Time): 23.01.2023 00:00:00  
 To (Date/Time): 23.01.2023 23:59:59

Log Triggered By  
 User:   
 Transaction code:   
 Program:

Log Class  
 Only very important logs  
 Only important logs  
 Also less important logs  
 All logs

Log Creation  
 Any  
 Dialog  
 In batch mode  
 Batch input

Log Source and Formatting  
 Format Completely from Database  
 Format Only Header Data from Database  
 Format Completely from Archive


Display logs

Date/Time/User	External ID	Object_Text	Subobject_Text	Trans...
2023-05-09 07:19:51 SCORYF	5	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 07:19:55 SCORYF	7	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 07:19:56 SCORYF	229	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 07:28:09 SCORYF	5	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 08:10:14 SCORYF	2	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 08:10:19 SCORYF	7	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 08:10:19 SCORYF	235	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:15:30 SCORYF	2	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:15:32 SCORYF	13	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:46:03 SCORYF	13			
2023-05-09 09:46:08 SCORYF	241	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:46:08 SCORYF	247	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:51:57 SCORYF	7	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:51:59 SCORYF	4	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:51:59 SCORYF	13	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:54:19 SCORYF	253	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:54:21 SCORYF	4	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:54:21 SCORYF	19	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 09:54:21 SCORYF	259	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 10:01:39 SCORYF	4	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 10:01:42 SCORYF	265	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC
2023-05-09 10:01:43 SCORYF	13	/ITR/SNAPSHOT...	RDM-StagingLogs	/ITR/CUSTSYNC

Type Message Text  
 000000000044012  
 /ITR/CREQUE\_INFO ObjectKey: 100Z2RDM-CR-0000000001166 0 -> 20230509 091532  
 /ITR/CREQUE\_INFO ObjectKey: 00000000000000000000000000000000 -> 20230509 091532  
 /ITR/CREQUE\_INFO ObjectKey: 100Z2RDM-CR-0000000001167 0 -> 20230509 091532  
 /ITR/CREQUE\_INFO ObjectKey: 00000000000000000000000000000000 -> 20230509 091532  
 /ITR/CREQUE\_INFO ObjectKey: 00000000000000000000000000000000 -> 20230509 091532

If for example an object is created with entries that do not exist in the receiver system (please also check the next chapter), the IDoc monitoring will show an error (status 51).


**IDoc Selection**



IDoc number: 64001, Status: 51, Message Type: /ITG/GENERIC, Status text: T024D ForeignKey-Inconsistencies -> Details: Tx SLG1! (Object=/I...), Partner No.: ID1100

IDoc number: 64009, Status: 51, Message Type: /ITG/GENERIC, Status text: T024D ForeignKey-Inconsistencies -> Details: Tx SLG1! (Object=/I...), Partner No.: ID1100

**IDoc Details**




IDoc number: 64001, Direction: 2 Inbound, Status: 51 Application document not posted, Message: T024D ForeignKey-Inconsistencies -> Details: Tx SLG1! (Object=/ITR/, SubO

**Techn.Info**

Code	SAP	Message number	000	Message type	E
ID	/ITG/GENERIC				
Text	& & & .				
1st parameter	T024D				
2nd parameter	ForeignKey-Inconsistencies -> Details: Tx SLG1!				
3rd parameter	(Object=/ITR/, SubObject=/ITR/CUSTSYNC)				
4th parameter					

The logging in SLG1 shows which entry has not been processed.



Log entries:

- 02.08.2023 10:09:05 SCORYF 6 /ITR/SNAPSHOT... RDM-StagingLo... /ITR/CUSTSYNC /I
- 02.08.2023 10:09:05 SCORYF 0 RDM ... Data Replicatio... Direct /I
- 02.08.2023 10:09:05 SCORYF 0 /ITR/SNAPSHOT... RDM-StagingLo... /ITR/CUSTSYNC /I
- 02.08.2023 10:09:05 SCORYF 0 RDM ... Data Replicatio... Direct /I
- 02.08.2023 10:09:05 SCORYF 0 /ITR/SNAPSHOT... RDM-StagingLo... /ITR/CUSTSYNC /I
- 02.08.2023 10:09:05 SCORYF 0 RDM ... Data Replicatio... Direct /I


**Message Text**

0000000000064001
T024D ObjectKey: 100PL1 U5 -> 20230802 100905
Entry SCY_1 Profit Center CEPC does not exist in PRCTR (check entry)
0000000000064009
T024D ObjectKey: 100U1 U6 -> 20230802 100905
Entry U1 Plant T001W does not exist in WERKS (check entry)

### 2.1.12 Foreign Key Check – Use Cases

The “Foreign Key Check” allows to check for inconsistencies in the context of the object types which have been replicated. The functionality depends on the use case which can either be a use case from the Reference Data Governance (IT Alternative or Governance Alternative) or from the Reference Data Harmonization. It allows the user to check if other objects which do have dependencies to the replicated object type are missing.

Missing entries should have been harmonized or need to be created in the receiver system.



#### 2.1.12.1 Foreign Key Check for IT Alternative

When creating for example a MRP Controller using the “Full IT Governance Alternative” all inconsistencies in the receiver will be shown in the Local Staging Area. The red cross in column “Foreign Key” will indicate when entries are missing.

Records selected: 0089											
Object	ObjectName	LocalTable	TableName	StagTable	Hier.	LocalEntries	StagEntries	LocAddEnt	StagAddEnt	Cust-Tx	ForeignKey
/ITR/BTDIP	RDM: MRP Controller	T024D	MRP Controllers	/ITR/T024D	1	29	1			5	X

After clicking the red cross, details are displayed. In the example below a profit center and a plant are missing.

RDM: Show Staging

```
/ITR/T024D
400K1 T1 Test 1307 +4923456789 TIM
    PRCTR Entry PRCTR02 Profit Center CEPC does not exist in PRCTR (check entry) -> CEPC
400K1 T1 Test 1307 +4923456789 TIM
    WERKS Entry K1 Plant T001W does not exist in WERKS (check entry) -> T001W
```

### 2.1.12.2 Foreign Key Check for Business Alternative

If an inconsistency occurs for an object type which has been configured for the "Business Alternative" (Direct Update) the logging of the error can be found in the IDoc Monitoring and the Application Logging as shown in chapter "Logging Business Governance Alternative".

### 2.1.12.3 Foreign Key Check for Reference Data Harmonization

To check the foreign keys in the Reference Data Harmonization scenario, use the "Check" Mode in the RDH Cockpit. Select the snapshot and click the foreign key button on the upper right.

RDH: Show/Activate SnapShot(s)

Choice

IndexId		to	
Version		to	
Table		to	
Date	06.07.2023	to	20.07.2023

Results: 0065

ID	Table Name	DB-Entr. AD-Entries	Short Description	MainIndex	AddrIndex
->ID110020230717073405	T024D	11	MRP Controllers	T024D073405	
	T880	5	Global Company Data (for KONS Ledger)	T880073405	
->ID110020230717073515	T002	1	Language Keys (Component BC-I18)	T002T073515	
	T002T	1672	Language Key Texts	T002T073515	
	T004	33	Directory of Charts of Accounts	T004T073515	
	T004T	77	Chart of Account Names	T004T073515	
->ID110020230717074126	T024D	11	MRP Controllers	T024D074126	
	T880	5	Global Company Data (for KONS Ledger)	T880074126	
->ID110020230720090453	J_1BTREGXT	8	Tax region description	J_1BTREGXT090453	
->ID110020230720103307	TVTWTI	2	Organizational Unit: Distribution Channels: Texts	TVTWTI103307	
->ID110020230720105150	TVTW	1	Organizational Unit: Distribution Channels	TVTW105150	
	TVTWTI	2	Organizational Unit: Distribution Channels: Texts	TVTWTI105150	
->ID110020230720135458	T024D	11	MRP Controllers	T024D135458	
	T880	5	Global Company Data (for KONS Ledger)	T880135458	

Now the Foreign Key Check is displayed and a red cross indicates missing entries.

ID	ID	Table Name	DB-Entr.	AD-Entries	Short Description	MainIndex	AddrIndex	User Name	Program Current Date	Time	SAP System	Mandt	Act-User	Act-Date	Act-Time	ForeignKey
>ID1100202307170734.		T024D	11	MRP Controllers	T024D073405	SCORYF	RDH	17.07.2023	07:34:05	ID1	100		00:00:00			
		T880	5	Global Company Data (for KONS Ledger)	T880073405	SCORYF	RDH	17.07.2023	07:34:05	ID1	100		00:00:00			
>ID1100202307170735.		T002	1	Language Keys (Component BC-118)	T002073515	SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00			
		T002T	1672	Language Key Texts	T002T073515	SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00			
		T004	33	Directory of Charts of Accounts	T004073515	SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00			
>ID1100202307170741.		T004T	77	Chart of Account Names	T004T073515	SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00			
		T024D	11	MRP Controllers	T024D074126	BOETTCHER	RDH	17.07.2023	07:41:26	ID1	100		00:00:00			
		T880	5	Global Company Data (for KONS Ledger)	T880074126	BOETTCHER	RDH	17.07.2023	07:41:26	ID1	100		00:00:00			
>ID1100202307200904.		J_1BTREGX	8	Tax region description	J_1BTREGX090453	SCORYG	RDH	20.07.2023	09:04:53	ID1	100		00:00:00			
		TVTW1T	2	Organizational Unit: Distribution Channels: Texts	TVTW1T03307	SCORYG	RDH	20.07.2023	10:33:07	ID1	100		00:00:00			
>ID1100202307201051.		TVTW1	1	Organizational Unit: Distribution Channels	TVTW105150	SCORYG	RDH	20.07.2023	10:51:50	ID1	100		00:00:00			
		TVTW1T	2	Organizational Unit: Distribution Channels: Texts	TVTW1T05150	SCORYG	RDH	20.07.2023	10:51:50	ID1	100		00:00:00			
>ID1100202307201354.		T024D	11	MRP Controllers	T024D135458	SATTLERU	RDH	20.07.2023	13:54:58	ID1	100		00:00:00			
		T880	5	Global Company Data (for KONS Ledger)	T880135458	SATTLERU	RDH	20.07.2023	13:54:58	ID1	100		00:00:00		✖	
															✓	

After clicking the red cross, details are displayed. In the example below a profit center, a plant and two recipient types are missing.

RDH: Show/Activate SnapShot(s)
RDH: Show/Activate SnapShot(s)
T024D
1002NW1MC1MRP Contr one 9669968927 REC1
USRTP Entry AG Recipient type T7790 does not exist in USRTYP (check entry) -> T7790
1002NW1MC1MRP Contr one 9669968927 REC1
WERKS Entry ZNW1 Plant T001W does not exist in WERKS (check entry) -> T001W
1002NW1MC3MRP Controller 3 9669968927 REC1
PRCTR Entry 0000000456 Profit Center CEPC does not exist in PRCTR (check entry) -> CEPC
1002NW1MC3MRP Controller 3 9669968927 REC1
USRTP Entry AG Recipient type T7790 does not exist in USRTYP (check entry) -> T7790
< > ...

## 2.1.13 Data Transfer

RDM delivers content for the extraction of Reference Data from SAP business systems as well as content for the data import of the data to RDM.

To start the extraction of Reference Data, you need to be logged on in the corresponding ERP client. Execute transaction MDMGX and press "Start Extraction". The following screen shows up, allowing you to define the extraction settings:

SAP MDM Generic Customizing Extractor



Deposit. Name (Code)			
Object Type			
Address of FTP Server			
MDM Root			
Port Name (Code)		to	
Process Level(0,1,2....)	0		
<input type="checkbox"/> Local download <input type="checkbox"/> Download to Appl. Server <input type="checkbox"/> File directory <input type="checkbox"/> Download in MDM port structure  <input type="checkbox"/> Upload via FTP			
User			
Password	*****		

In the "Deposit. Name (Code)" field, use the F4-help and choose the object that you want to extract. Then enter your preferred download settings (e.g. local download on your computer or upload via FTP" and press execute. 

The next screen shows up, displaying the XML files which have been created. Store the name and location of the files. Note: During the extraction, a transformation is executed which can be enhanced using table /ITR/ENT\_TRANSF, if the data model has been enhanced (supported for Type 1 entities only).

After the extraction is done, log in to the RDM client and execute transaction CG3Z. The following screen pops up, allowing you to define which files should be transferred to which directory:

Upload File: Parameters

Source file on front end	Z:\MATKL_ECC_554_ITT400.xml	
Target file on application server	/usr/sap/ITT/MDG_DATA_IMPORT/MATKL_ECC_554_ITT400.xml	
Transfer format for data	BIN	<input checked="" type="checkbox"/> Overwrite file

Fill out the fields according to your system landscape:

- "Source file on front end": [Path of the file that you want to upload]

- “Target file on application server”: E.g. “/usr/sap/MDG\_DATA\_IMPORT/[name of the file that you want to upload]” depending on your system landscape and the settings provided in the Data Import settings (see MDGIMG/General Settings/Data Transfer).

Then press upload. Repeat this process for all files which have been generated by the extraction.

After you are done and before importing the data, consider turning off the data replication. This can be done by executing transaction DRFIMG, navigating to “Define Custom Settings for Data Replication” → “Define Replication Models”. In the settings, tag the replication model “RDM” and press “Deactivate”.

After you are done, open the RDM launchpad and press “Import Master Data” in section “Data Transfer”, or execute transaction DTIMPORT. The following screen shows up, allowing you to import the data stored in the previously created files:

The screenshot shows the SAP R/3 Import Master Data and Mapping Information dialog box. The dialog is divided into several sections:

- Import Settings:** Contains fields for Object Type (dropdown), Description (text input), Overwrite (checkbox), and Custom Converter (text input).
- Governance Settings:** Contains fields for Governance (checkbox), Post Processing (dropdown set to "Manual Post Processing"), Change Request Type (text input), and Edition (text input).
- Scheduling Settings:** Contains fields for Scheduling (dropdown set to "Import Now"), Date (text input), and Time (text input set to "00:00:00").
- Parallel Processing Settings:** Contains fields for Parallel Processing (checkbox), Queue name (text input), and Number of Processes (text input set to "0").
- Data Sources:** A table with columns "Object Type" and "Source Directory". It includes buttons for Add, Delete, and Show Directory Content.

In “Import Settings” / “Object Type”, choose the object type. For “Description”, provide a brief description of what you are going to upload.

The “Overwrite” checkbox lets you decide if the data import should overwrite an already existing entry if the import files contain a duplicate entry, or if it should ignore the duplicate entry.

In “Scheduling Settings”, you can decide whether you want to import the data immediately or at any other given point in time.

---

Using "Governance Settings", you can decide which change request type you want to use.

In "Parallel Processing Settings", you can decide if you want to allow parallel processing or not.

After providing the import settings, press "Add" in the "Data Sources" table and choose the corresponding object type. Then select the source directory (e.g. "MDG\_DATA\_IMPORT"). You can also check the files in the source directory by pressing on "Show Directory Content".

Press "Import" to import the data and on "Display Monitoring" to track the import process and verify that the process is successfully executed. The data has now been imported. You can view it by navigating to the object search page via the launchpad.

#### 2.1.14 Deleting Objects

**Note:** a functionality for deleting objects in RDM is **not** delivered out of the box. If a client requests this kind of functionality, Itego can help implementing it on a project basis. For further information about this topic, contact [support@itego.de](mailto:support@itego.de) – Subject: "RDM Deletion".

The following screenshots therefore only provide a preview of how the deletion in RDM could work.

In order to delete a certain object, start on the RDM launchpad and press on the corresponding object type. The object search page is displayed:

**Search: Material Group**

Search Method:

**Search Criteria** Saved Searches:

Material Group	is				
Description (short text)	is				
Description (long text)	is				
Division	is				

Maximum Number of Results:

Save Search As:

Press on the object, you want to delete. The object overview page is displayed:

Process Object with MDG

Save | Cancel | **Delete**

**Audit Information**

Audit Information

Created On: 26.12.2018 13:07:34

Changed On:

Approved On: 26.12.2018 13:16:43

**Material Group**

**Material Group**

Material Group: 00000032

Description (short text): 00000032

Description (long text): MatGrp32

**Material Group Descriptions**

New | Copy | **Edit**

Actions	Language Key	Description (long text)
 	EN	MatGrp32

Press on "Delete". A popup shows up, asking you to confirm your action. Press on "Yes". A page shows up, asking you to provide information for the change request header.

Process Object with MDG

Save **Submit** Cancel Check

Entity 00000032 of entity type MATKL will be deleted with this change request

Change Request [Edit](#)

General Notes Attachments

General Data

Change Request ID:	7534	Process Data
* Description:	<input type="text"/>	
Priority:	<input type="text"/>	
Due Date:	<input type="text"/>	
Reason:	<input type="text"/>	

Audit Information

Audit Information

Created On:	26.12.2018 13:07:34
Changed On:	
Approved On:	26.12.2018 13:16:43

Material Group

To finalize the process, fill out the required fields of the change request header (in this case: "Description") and press on "Submit".

The delete request is now released.

## 2.1.15 Exceptions

This section contains information on objects whose processing differs from the standard instructions.

### 2.1.15.1 Product Hierarchy

The maintenance of a Product Hierarchy differs from the standard process, as this object type is maintained in hierarchy levels. On the RDM launchpad, you will notice that at least two apps are linked:

- **Product Hierarchy Name:** Create and maintain (change) the structure of the Product Hierarchy, but not the nodes in the hierarchy. Maintenance is done using the "Hierarchy Processing".
- **Product Hierarchy Nodes:** Define the nodes in the Product Hierarchy on various levels (e.g. Raw Materials, Transportation, ...). Nodes can be assigned to a Product Hierarchy created in "Product Hierarchy Name".

*Optional:*

- **Product Hierarchy Subnodes:** Optionally, subnodes can be defined for nodes on the lowest level of the hierarchy. However, this is not mandatory, as a node can also function as the final level in the product hierarchy without any subnodes. This app can be removed from the Fiori Launchpad if it is not needed.


The next sections describe how to create or change nodes in the single object maintenance app ("Product Hierarchy Nodes") working on one node at a time or in the multiple node processing apps ("Product Hierarchy Name" or "File Download / File Upload")

### 2.1.15.1.1 Single Object Maintenance (Product Hierarchy Nodes)


#### 2.1.15.1.1.1 Create Node

Select Product Hierarchy Nodes app, optionally search for nodes and finally select "New" and create a change request.


Choose a description, the product hierarchy level of the node, and enter the external number. The "Higher Level" field is automatically filled after the hierarchy assignment and contains the external number of the parent node:



You can manually add the Hierarchy Assignment or choose it from the tree-structure (click the icon in column "Actions"):



In the “Current Node” field, enter the number for the current level, which will then be appended to the higher-level number:



The screenshot shows the 'Product Hierarchy' edit screen. The 'Product Hierarchy Node' section is expanded, showing the following fields:

- Product Hierarchy Level: **4** Type
- Product Hierarchy Node ID: **45000201**
- Description (long text): **TypeA Demo**
- External Number: **50AE002**
- Higher Level: **50AE002**
- Current Level: **001**

The 'Descriptions' section is also visible, showing a table with one row:

Actions	Changes	Language Key	Product Hierarchy Node	Product hierarchy text
<input type="button" value="New"/>	<input type="button" value="Copy"/>	EN	45000201	TypeA Demo


The 'Hierarchy Assignment' section is expanded, showing a table with one row:

Actions	Changes	Hierarchy	Description	Parent Type	Parent Node	Description	Previous Type	Previous Node	Description
<input type="radio"/>	<input type="radio"/>	ProdHrchy	ProdHrchy	Product Hierarchy	30000301	Drilling Machines Demo			

After this, submit the Change Request to start the approval process.


#### 2.1.15.1.1.2 Change Node

In the search choose a the node that should be changed:



<input type="checkbox"/>	Pending...	Product Hierarchy...	Description (long text)	External Number	From Edition
<input type="checkbox"/>	40000003	Spray Guns	0101002002	PRDH	
<input type="checkbox"/>	40000004	Cleaning Equipment	0101002003	PRDH	
<input type="checkbox"/>	40000060	Beer	1401D01001	PRDH	
<input type="checkbox"/>	40000061	Wine	1401D01002	PRDH	
<input checked="" type="checkbox"/>	<b>50000000</b>	SD-Series 1	01010010010001	PRDH	
<input type="checkbox"/>	50000001	DM-Series 1	01010010020001	PRDH	

Click “Edit”, modify the entries as needed and submit the change request:




The screenshot shows the 'Product Hierarchy' edit screen. The 'Product Hierarchy Node' section is expanded, showing the following fields:

- \* Product Hierarchy Level: **5** Series
- Product Hierarchy Node ID: **50000000**
- Description (long text): **SD-Series 2**

### 2.1.15.1.2 Multiple Object Processing: Hierarchy Processing (Product Hierarchy Name)


Select Product Hierarchy Name app, search for the Product Hierarchy Name and click "Hierarchy Processing":



Result List: 1 record found

<input type="checkbox"/> Pending...	Product Hierarchy N...	Valid-From Date	Valid-To Date	Rank
<input checked="" type="checkbox"/>	ProdHrchy	01.07.2022	31.12.9999	

To show the whole tree you can expand the Product Hierarchy:




Display As: Hierarchy

Levels

Prod Hier. Node	External Number	Approved E
ProdHrchy		
10000060		IT_ALL_06
20000060	01	IT_ALL_06
30000060	01D01	IT_ALL_06
40000060	01D01001	IT_ALL_06
50000060	1401D010010001	IT_ALL_06
60000060	1401D010010001	IT_ALL_06

With "Find" you can search for the nodes. You can enter the node number (internal) or the description.




Display As: Hierarchy

Find in Hierarchy

Search Term: Screwdrivers

Prod Hier. Node	Description (Long)	External Number	Approved By User	Pending CR	Changes	Nex
ProdHrchy						
10000060	DCME	14	IT_ALL_06			
10000000	ACME	01	IT_ALL_06			
20000000	Tools	0101	IT_ALL_06			
30000000	Electrical Parts	0101001	IT_ALL_06			
40000000	Screwdrivers	0101001001	IT_ALL_06			
50000000	SD-Series 1	01010010010001	IT_ALL_06			

If the hierarchy has been changed (for example by an additional load of hierarchy nodes), you can refresh the hierarchy to show the most up to date version:



Edit Refresh Switch to Active Version New Selection

Inactive Version Entity Type: Product Hierarchy Node Edition: PRDH (Product Hierarchy Edition) Valid-From Date

Display As: Hierarchy

With "Display as List" it is possible to view the hierarchy as a list instead. In this view the list can be exported as an Excel file:

Prod Hier. Node	Desc. Long	Approved By Username	Approved By Full Name
10000000	ACME	IT_ALL_06	IT_ALL_06
10000060	DCME	IT_ALL_06	IT_ALL_06
20000000	Tools	IT_ALL_06	IT_ALL_06
20000060	Krombacher	IT_ALL_06	IT_ALL_06

To edit the Hierarchy, select "Edit" and you will get the opportunity to either create a new change request or to reuse an already existing change request. The next sections will show some use cases which will be saved in the selected change request.

#### 2.1.15.1.2.1 Move Nodes

You can move nodes using drag-and-drop. When doing so, please note that nodes can only be moved within the same hierarchy level. For example, a Level 3 node can only be moved to a different position within Level 3, but not below or above nodes from other levels.

Alternatively, you can use the menu option "Edit" → "Cut" and to insert the node use "Paste" or "Paste at Lower Level". The option you choose depends on where you want to assign the node within the hierarchy.

Prod Hier. Node	Description (Long)	External Number	Approved By User	Pending
10000000	ACME	01	IT_ALL_06	08.09.2
20000000	Tools	0101	IT_ALL_06	08.09.2
30000000	Electrical Parts	0101001	IT_ALL_06	08.09.2
40000000	Screwdrivers	0101001001	IT_ALL_06	08.09.2
50000000	SD-Series 1	01010010010001	IT_ALL_06	08.09.2

You can also move the node using the arrow buttons. The left and right arrows adjust the node's level, moving it to a higher or lower position within the hierarchy.

### 2.1.15.1.2.2 Insert (Assign) Nodes

Select the node below which you want to insert a node. You can then insert a node, for example after creating a node without a hierarchy assignment, by selecting “Insert”. In the insert options, choose “Prod Hier Node (Unassigned)” to assign the unassigned node into the hierarchy.

Find the node you want to insert, select it, and click Transfer. If you want to insert the node one level below, select “Insert as Subnode”.

### 2.1.15.1.2.3 Change Node Description

After moving a node, save your changes and create a Change Request. You can then add further processing steps in the Change Request, such as renaming nodes. To do this, open the Change Request either from your inbox or directly within the Hierarchy Assignment view via the “Pending CR” icon (clock).

Prod Hier. Node		Description (Long)	External Number	Approved By User	Pending CR	Chan
<input type="checkbox"/>	ProdHrchy					
<input type="checkbox"/>	> 10000060	DCME	14	IT_ALL_06		
<input type="checkbox"/>	10000000	ACME	01	IT_ALL_06		
<input type="checkbox"/>	20000000	Tools	0101	IT_ALL_06		
<input type="checkbox"/>	30000000	Electrical Parts	0101001	IT_ALL_06		
<input type="checkbox"/>	> 40000000	Screwdrivers	0101001001	IT_ALL_06		
<input type="checkbox"/>	40000001	Drilling Machines	0101001002	IT_ALL_06		
<input type="checkbox"/>	50000001	DM-Series 1	01010010020001	IT_ALL_06		
<input checked="" type="checkbox"/>	60000001	SD-18V-200	010100100100010002	IT_ALL_06		

In column "Objects" choose "Product Hierarchy Node":

Objects	
Entity Type	Number
Product Hierarchy Node	0
Product Hierarchy Sub Node	0

Select Add Row and then search for the Node:

Search: Prod Hier. Node	
Product Hierarchy Node: <input type="text"/>	
Items (31)	
Product Hierarchy Node	Name (Long)
<input type="checkbox"/> 5000060	Munich Helle
<input type="checkbox"/> 5000061	Pils
<input type="checkbox"/> 5000062	White Wine
<input type="checkbox"/> 6000000	SD-18V-100
<input type="checkbox"/> 6000001	SD-18V-200
<input type="checkbox"/> 6000002	DM-500 Plus


Select the row and click Single Processing:

Product Hierarchy Node: Objects to Be Changed					
Export	Single Processing	Mass Change	Add Row	Delete Row(s)	Display Changes
<input type="checkbox"/> Prod Hier. Node					Description
<input type="checkbox"/> 60000001					SD-18V-200

Select "Edit" and change the description. Save your entries:

#### 2.1.15.1.2.4 Remove Nodes

To remove a node from the hierarchy select "Edit" → "Remove". This will delete the assignment of the node to the hierarchy but not the node itself. It can be re-assigned to the hierarchy at a later point in time.



#### 2.1.15.1.2.5 Delete Nodes

To entirely delete a node, select the node and choose "Delete".

### 2.1.15.1.3 Multiple Object Processing: Hierarchy Processing (File Download and File Upload)

Product Hierarchy nodes (including language dependent texts) and hierarchy assignments (the hierarchy structure) can be downloaded and uploaded.

After choosing the File Download app, the three steps to download a complete hierarchy are:

1. Download nodes: variant ITR\_PRODN (Product Hierarchy Node)
2. Download hierarchy assignments: variant ITR\_PRODNH (Prod. Hier. Node Hierarchies)
3. Download texts: variant ITR\_PRODNT (Product Hierarchy Node Text)

**Note:** these are the delivered file variants which can be used either as is or as a template to create your own variants.

## Nodes:

1 **Determine Entity Type** 2 Define Selection 3 Define File Structure 4 Determine Download Settings 5 Check and Execute

**General Settings**

\* Entity Type: Product Hierarchy Node  
 \* Type of Transfer: Attributes  
 \* Edition: PRDH  Product Hierarchy Edition

**Variant**

Variant: ITR\_PRO...  RDM - Upload Product Hierarchy Node

## Hierarchy Assignments:

**General Settings**

\* Entity Type: Product Hierarchy Node  
 \* Type of Transfer: Hierarchies  
 \* Edition: PRDH  Product Hierarchy Edition

**Variant**

Variant: ITR\_PRO...  RDM - Upl. Prod. Hier. Node Hierarchies

## Texts:

**General Settings**

\* Entity Type: Product Hierarchy Node  
 \* Type of Transfer: Language-Dependent Texts  
 \* Edition: PRDH  Product Hierarchy Edition

**Variant**

Variant: ITR\_PRO...  RDM - Upload Product Hierarchy Node Text

After saving these files they can be used as templates for changing the product hierarchy structure or the set of nodes used in the product hierarchy. Choose the File Upload app and choose the same variants which have been used for the download to upload the new data.

After the Upload Settings have been specified, choose one of the available change request types, check the data and finally execute the upload process and (optionally) approve the data to be loaded:

## Example: Loading new nodes



**General Settings**

\* Entity Type: Product Hierarchy Node

\* Type of Transfer: Attributes

\* Edition: PRDH     Product Hierarchy Edition

**Variant**

Variant: ITR\_PRO...  RDM - Upload Product Hierarchy Node

Upload settings including the selection of the file to be uploaded:



1 Determine Entity Type    2 Define File Structure    3 Determine Upload Settings    4 Check and Execute

**Upload Settings**

\* Upload Mode: Overwrite or Add Attributes

\* Conversion: Execute Conversion

**File Store**

\* File System: Presentation Server

\* File Name: C:\fakepath\Tools No...  Load File

**File Format**

\* Separator: Semicolon

Comment Row: \*

Checking the data after selecting the change request type and finally executing the upload process:

**Data**

Show: All Rows

Product Hierarchy Node	Description (long text)	External Number	Prod.Hier. Level
10000000	ACME	01	1
20000000	Tools	0101	2
30000000	Electrical Parts	0101001	3
40000000	Screwdrivers	0101001001	4
50000000	SD-Series 1	01010010010001	5
60000000	SD-18V-100	010100100100010001	6
60000001	SD 18V 200	010100100100010002	6


#### 2.1.15.1.4 Data Replication (Product Hierarchy Name)

**Note:** Data Replication is executed only when it is started manually.

Start the app “Product Hierarchy Name”, search and select “Replicate”:


Result List: 1 record found					
		Change Documents	Replication Status	Replicate	Hierarchy Processing
<input checked="" type="checkbox"/>	Pending...	Product Hierarchy N...	Valid-From Date	Valid-To Date	Rank
<input checked="" type="checkbox"/>	ProdHrchy	01.07.2022	31.12.9999		

Choose your Target System and click “Replicate”:



System ID	Description
IH2400	IH2400
IR1200	IR1200
IR2200	IR2200

After the replication has been executed, you can check the replicated data using transaction “SPRO” (search for “Define Product Hierarchies”) or use transaction OVSV:



System ID	Description
IH2400	IH2400
IR1200	IR1200
IR2200	IR2200

SAP Display View "Materials: Product Hierarchies": Overview		
Product Hierarchy	Level No.	Description
00001	1	Tools
0000100001	2	Electrical parts
00001000010000001	3	Screwdrivers
00001000010000002	3	Drilling machines
0000100002	2	Compressors
00001000020000001	3	Nail guns
00001000020000002	3	Spray guns
00001000020000003	3	Cleaning equipment
00002	1	Drinks
0000200001	2	Alcoholic
00002000010000001	3	Beer
00002000010000002	3	Wine
0000200002	2	Non-alcoholic
00002000020000001	3	Juice
00002000020000002	3	Water
0000200003	2	Accessories
00002000030000001	3	Glasses

### 2.1.15.2 Payment Terms

The maintenance of Payment Terms differs from the standard process, as this object is maintained in two objects, which are both linked on the launchpad:

- **Payment Terms:** A Payment Term is an object, which defines the payment terms and conditions for certain time periods. It can be created and used independently.
- **Payment Terms Details:** Payment Terms Details, also called "day limit", is an object, which allows to define more detailed terms of payments. It cannot be created independently and therefore needs to be assigned to a Payment Term, which is done in the creation process.

### 2.1.15.3 Exchange Rates

The maintenance of Exchange Rates differs from the standard process as RDM offers additional functionalities. As exchange rates change frequently and simultaneously, they are rarely maintained manually, but rather automatically. For those reasons, RDM offers the possibility of importing and validating exchange rates automatically. It is also possible to include a data steward or specialist into this process to check on the imported exchange rates.

Information on how to set up and use the import process can be found in a separate document for "Exchange Rates".

---

## 2.2 Roles and Authorizations

The following roles are delivered and can be used as templates for your own role definition and authorization profiles. Authorization profiles define which reference data object can be processed with which change request type and which user role is able to see which data.

All roles use the menu role "/ITR/ITEGO\_MDG\_RDM\_MENU\_<n>".

### 2.2.1 Display

Role: /ITR/ITEGO\_MDG\_RDM\_DISP\_<n>

Role with limited authorizations. Data can only be displayed.

### 2.2.2 Requester

Role: /ITR/ITEGO\_MDG\_RDM\_REQ\_<n>

Requesters can request the creation or a change of a reference data object. The Requester submits a change request and might be involved in the change request processing again if one of the users involved sends the change request back to the requester "For Revision".

### 2.2.3 Data Specialist

Role: /ITR/ITEGO\_MDG\_RDM\_SPEC\_<n>

Data Specialists process the change request which has been created by the Requester. They might add additional data and forward the change request to the Data Steward. They also might send the change request to the Requester for revision.

### 2.2.4 Data Steward

Role: /ITR/ITEGO\_MDG\_RDM\_STEW\_<n>

Data Stewards are responsible for checking the data quality and consistency of the requested reference data object and approve, reject or send the change request for revision to the Data Specialist.

---

## 2.2.5 Local Staging Administrator

These following roles are used for the maintenance of the local staging area:

Role: /ITR/MDG\_STAGING\_<n>

This role can only display, it is not authorized to administrate or restore.


Role: /ITR/MDG\_LSA\_ADMIN

This role can display and administer. It is not authorized to restore snapshots.

Role: /ITR/MDG\_LSA\_SNAPSHOT\_MNG

This role can display, administer and restore snapshots.

### 3 Working with Reference Data Management, Harmonization



The primary purpose of Reference Data Harmonization (RDH) is to ensure that data remains harmonized and synchronized across various systems. To achieve this, the solution offers multiple options for replication with optional field reduction, additional code or overwrite protection, all of which can be logged and monitored for transparency and control.

In the first step of data harmonization, data can be consolidated from one or more systems into RDM.

After data consolidation, the next step is synchronization. Data synchronization ensures that data in RDM is accurately propagated to other systems as required. This process can involve multiple systems as sources and destinations.


To enable flexible data transport, RDH offers three replication options, each designed for specific use cases. These options provide control, additional features, and flexibility in managing data transfers:

- The "Business Harmonization" (Direct Update – Single/Bundle) option writes entries directly to the tables in the receiver systems. It is a straightforward and quick method for transferring data without extensive processing.
- The "IT Harmonization" (Snapshot) option provides additional functionalities beyond simple data replication. It allows to compare entries, create backups, activate, or delete snapshots in the receiver systems.
- The "Transport" option is another method for data replication. This option is useful when you need to package data and transport it in a controlled manner. It allows for

the creation of data packages that can be deployed at specific times or to specific destinations.


### 3.1 The RDH Cockpit

The RDH Cockpit, accessed through transaction /ITR/RDH\_COCKPIT, serves as a comprehensive cockpit for sending and receiving systems.



The screenshot displays two side-by-side sections of the SAP RDH-Cockpit interface. The left section is titled 'SAP RDH-Cockpit: SendMode' and the right section is titled 'SAP RDH-Cockpit: ReceiveMode'. Both sections have a dark header bar with the SAP logo and the title. Below the header are two main sections: 'Groups and Foreign Keys' and 'Send, Check and Activate'. The 'Groups and Foreign Keys' section contains buttons for 'Configuration Groups', 'Foreign Keys', 'Business Objects', and 'Recreate Foreign Keys'. The 'Send, Check and Activate' section contains buttons for 'Send', 'Monitoring', 'Check', and 'Logging'. Both sections have a small 'Help' button in the top right corner. The right section, 'ReceiveMode', also includes a 'Send/Receive' button in its header.

In addition to the send and receive functions, the RDH cockpit provides an expert mode which offers additional functionality.



The screenshot shows the SAP RDH-Cockpit interface in Expert mode. The header bar includes the SAP logo and the title 'SAP RDH-Cockpit: Expertmode'. Below the header are three main sections: 'Groups and Foreign Keys', 'Send, Check and Activate', and 'Settings'. The 'Groups and Foreign Keys' section contains buttons for 'Configuration Groups', 'Foreign Keys', 'Business Objects', and 'Recreate Foreign Keys'. The 'Send, Check and Activate' section contains buttons for 'Send', 'Monitoring', 'Activate', and 'Logging'. The 'Settings' section contains buttons for 'Field Reduction', 'Enhancements', 'Overwrite Protection', and a 'Help' button. The 'Send, Check and Activate' section also includes a 'Send/Receive' button in its header.


## 3.2 Send Mode

### 3.2.1 Send Mode – Configuration Groups


Configuration Groups play a crucial role in organizing and managing the replication of data between systems. These groups provide a structured way to specify the object types and tables that need to be sent from a sending system to a receiving system. Pre-configured configuration groups are delivered through a BC-Set (please refer to the documentation "Reference Data Management - Configuration").

Configuration Groups allow the definition of key field limitations. This means that you can define filters, ensuring that only relevant data is considered in the replication process. The section below shows how to define such a group.

Create a Configuration Group by selecting "Configuration Group"



Create a new entry



Dialog Structure

RefData Harmonization - Groups

RefData Harmonization

New Entries

Configuration G.	Configuration Group Text
ACCOUNTS	Account 179100 from Chart of Accounts INT
ACCOUNTS-1	Account 176500 from Chart of Accounts INT
ACCOUNTS_REF	Reference Tables for Accounts
BILSTRU_FS_F	Distribution Financial Reporting structure FS_F
BILSTRU_REF	Reference Tables for FRS
BP_REF	Reference Tables for BP
BUS_PARTNER	Business Partner Master
CURRENCY	Currency-Rates
CUSTCL_TKUKL	Int Refer with Mapping (Customer Classifications)
CUSTOMER	Customer
CUSTOMER_SCY	Customer
FB-TEST-GR2	FB Test Group 2
FUNCTIONAREA	Functional Area
LGORTE	Storage Locations
MATERIAL	Materialstamm - MARA
MATTTYPE	Material Types
PAYMENT-TERM	Payment-Terms
RDM-OBJECTS	RDM-OBJECTS
RDM_OBJECTS	Reference Data Sync

Define a name for your configuration group and click enter

RefData Harmonization - Groups	
Configuration Group	Configuration Group Text
PAYMENTTERM	Payment Terms

Mark the configuration group and click "RefData Harmonization – Objects"

---



RefData Harmonization - Groups	
Configuration G.	Configuration Group Text
PAYMENTTERM	Payment Terms

## Create a new entry

RefData

Config

RefData Harmonization - Groups

RefData Harmonization - Objects

Enter the configuration group and the table names. Then click F4 in the Object key field.

Specify the key fields and click enter

The keys are shown in the overview. Click enter and save your entries

### 3.2.2 Send Mode – Check Foreign Keys

After creating and adding foreign keys, the next step involves their validation. This verification ensures the accuracy and completeness of foreign key relationships. By performing a check of foreign keys, you can identify any discrepancies or missing entries, preventing potential data inconsistencies during the replication process.

To check the foreign keys in the Reference Data Harmonization scenario, use the "Check" mode in the RDH Cockpit.

Select the Snapshot and click the foreign key button on the upper right

### RDH: Show/Activate SnapShot(s)

Choice

IndexId	<input type="text"/>	to	<input type="text"/>	
Version	<input type="text"/>	to	<input type="text"/>	
Table	<input type="text"/>	to	<input type="text"/>	
Date	<input type="text" value="06.07.2023"/>	to	<input type="text" value="20.07.2023"/>	

Results: 0065

ID	Table Name	DB-Entr.	AD-Entries	Short Description	MainIndex	AddrIndex
->ID110020230717073405	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D073405	
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880073405	
->ID110020230717073515	<b>T002</b>	<b>1</b>		Language Keys (Component BC-I18)	T002073515	
	<b>T002T</b>	<b>1672</b>		Language Key Texts	T002T073515	
	<b>T004</b>	<b>33</b>		Directory of Charts of Accounts	T004073515	
	<b>T004T</b>	<b>77</b>		Chart of Account Names	T004T073515	
->ID110020230717074126	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D074126	
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880074126	
->ID110020230720090453	<b>J_1BTREGXT</b>	<b>8</b>		Tax region description	J_1BTREGXT090453	
->ID110020230720103307	<b>TVTWT</b>	<b>2</b>		Organizational Unit: Distribution Channels: Texts	TVTWT103307	
->ID110020230720105150	<b>TVTW</b>	<b>1</b>		Organizational Unit: Distribution Channels	TVTW105150	
	<b>TVTWT</b>	<b>2</b>		Organizational Unit: Distribution Channels: Texts	TVTWT105150	
->ID110020230720135458	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D135458	
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880135458	

The Foreign Key Check is displayed, and a red cross indicates missing entries

ID	Table Name	DB-Entr.	AD-Entries	Short Description	MainIndex	AddrIndex	User Name	Program	Current Date	Time	SAP System	Mandt	Act-User	Act-Date	Act-Time	ForeignKey
->ID110020230717073405	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D073405		SCORYF	RDH	17.07.2023	07:34:05	ID1	100		00:00:00		
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880073405		SCORYF	RDH	17.07.2023	07:34:05	ID1	100		00:00:00		
->ID110020230717073515	<b>T002</b>	<b>1</b>		Language Keys (Component BC-I18)	T002073515		SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00		
	<b>T002T</b>	<b>1672</b>		Language Key Texts	T002T073515		SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00		
	<b>T004</b>	<b>33</b>		Directory of Charts of Accounts	T004073515		SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00		
	<b>T004T</b>	<b>77</b>		Chart of Account Names	T004T073515		SCORYF	RDH	17.07.2023	07:35:15	ID1	100		00:00:00		
->ID110020230717074126	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D074126		BOETTCHERM	RDH	17.07.2023	07:41:26	ID1	100		00:00:00		
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880074126		SCORYG	RDH	20.07.2023	07:35:15	ID1	100		00:00:00		
->ID110020230720090453	<b>J_1BTREGXT</b>	<b>8</b>		Tax region description	J_1BTREGXT090453		SCORYG	RDH	20.07.2023	09:04:53	ID1	100		00:00:00		
->ID110020230720103307	<b>TVTWT</b>	<b>2</b>		Organizational Unit: Distribution Channels: Texts	TVTWT103307		SCORYG	RDH	20.07.2023	10:33:07	ID1	100		00:00:00		
->ID110020230720105150	<b>TVTW</b>	<b>1</b>		Organizational Unit: Distribution Channels	TVTW105150		SCORYG	RDH	20.07.2023	10:51:50	ID1	100		00:00:00		
	<b>TVTWT</b>	<b>2</b>		Organizational Unit: Distribution Channels: Texts	TVTWT105150		SCORYG	RDH	20.07.2023	10:51:50	ID1	100		00:00:00		
->ID110020230720135458	<b>T024D</b>	<b>11</b>		MRP Controllers	T024D135458		SATTLERU	RDH	20.07.2023	13:54:58	ID1	100		00:00:00		
	<b>T880</b>	<b>5</b>		Global Company Data (for KONS Ledger)	T880135458		SATTLERU	RDH	20.07.2023	13:54:58	ID1	100		00:00:00		

Click the red cross to display the details. In the example below a profit center, a plant and two recipient types are missing


RDH: Show/Activate SnapShot(s)														
RDH: Show/Activate SnapShot(s)														
<b>T024D</b>														
1002NW1MC1MRP Contr one 9669968927 REC1														
<b>USRTRY</b> Entry AG Recipient type T7790 does not exist in USRTYP (check entry) -> T7790														
1002NW1MC1MRP Contr one 9669968927 REC1														
<b>WERKS</b> Entry ZNW1 Plant T001W does not exist in WERKS (check entry) -> T001W														
1002NW1MC3MRP Controller 3 9669968927 REC1														
<b>PRCTR</b> Entry 0000000456 Profit Center CEPC does not exist in PRCTR (check entry) -> CEPC														
1002NW1MC3MRP Controller 3 9669968927 REC1														
<b>USRTRY</b> Entry AG Recipient type T7790 does not exist in USRTYP (check entry) -> T7790														

### 3.2.3 Send Mode – Sending

The Send mode provides users with various sending modes to replicate data. It ensures flexibility in choosing the appropriate mode based on specific needs, such as direct table update, Snapshot, or creating a transport for entries:

- The "Business Harmonization" (Direct Update – Single/Bundle) option writes entries directly to the tables in the receiver systems. It is a straightforward and quick method for transferring data without extensive processing.
- The "IT Harmonization" (Snapshot) option provides additional functionalities beyond simple data replication. It allows to compare entries, create backups, activate, or delete snapshots in the receiver systems.
- The "Transport" option is another method for data replication. This option is useful when you need to package data and transport it in a controlled manner. It allows for the creation of data packages that can be deployed at specific times or to specific destinations.

In Send Mode click the tab "Send".



### 3.2.3.1 Single Mode

In Single Mode, individual entries are transmitted, providing a direct and focused approach for sending specific data. Choose the Configuration Group and choose "Single". For options choose e.g. "Logging", "Test" and "Detail List". Then click execute.

**SAP RDH: ReferenceDataHarmonization – Send Objects**

**ObjectSelection**

Table(s)	T052	to	<input type="text"/>	<input type="button" value=""/>
View(s)		to	<input type="text"/>	<input type="button" value=""/>
Objectgroup(s)	PAYMENT-TERM	to	<input type="text"/>	<input type="button" value=""/>

**ALE / WebService**

MessageType	/ITG/GENERIC
Logical System	IH2400
Port for WebService	

**Mode**

Transfer	<input checked="" type="radio"/> Single	<input type="radio"/> Bundle	<input type="radio"/> SnapShot	<input type="radio"/> Transport
----------	---	------------------------------	--------------------------------	---------------------------------

**Options**

Scope	<input type="radio"/> with address	<input checked="" type="radio"/> without address
Heterogen	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Logging	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input checked="" type="radio"/> Yes	<input type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No

In the test mode you can verify the contents in the provided list

**SAP Simulation in Testmode / Show TableKey(s)**




Table Name	Short Description	Number
<b>Table Name</b>		
T052	Terms of Payment	
T052	1000000100	100 D 0001 00
T052	1000000200	100 D 0002 00
T052	1000000300	100 D 0003 00
T052	1000000400	100 D 0004 00
T052	1000000500	100 D 0005 00
T052	1000000600	100 D 0006 00
T052	1000000715	100 D 0007 15
T052	1000000731	100 D 0007 31
T052	1000000815	100 D 0008 15
T052	1000000831	100 D 0008 31
T052	1000000900	100 D 0009 00
<b>T052U</b>		
T052U	Own Explanations For Terms of Payment	
T052U	1000000100	100 D 0001 00
T052U	1000000200	100 D 0002 00
T052U	1000000300	100 D 0003 00
T052U	1000000400	100 D 0004 00
T052U	1000000500	100 D 0005 00
T052U	1000000600	100 D 0006 00
T052U	1000000715	100 D 0007 15
T052U	1000000731	100 D 0007 31
T052U	1000000815	100 D 0008 15
T052U	1000000831	100 D 0008 31
T052U	1000000900	100 D 0009 00
T052U	100E000100	100 E 0001 00
T052U	100E000200	100 E 0002 00

### 3.2.3.2 Bundle Mode

Bundle Mode allows the replication of many records in one message (IDoc or Webservice), optimizing efficiency and organization in the data transmission process. Choose the Configuration Group and choose "Bundle". For options e.g. choose "Logging" and "Detail List". Then click execute.

**ObjectSelection**

Table(s)	T052	to	
View(s)		to	
Objectgroup(s)	PAYMENT-TERM	to	

**ALE / WebService**

MessageType	/ITG/GENERIC
Logical System	IH2400
Port for WebService	

**Mode**

Transfer	<input type="radio"/> Single	<input checked="" type="radio"/> Bundle	<input type="radio"/> SnapShot	<input type="radio"/> Transport
----------	------------------------------	---	--------------------------------	---------------------------------

**Options**

Scope	<input type="radio"/> with address	<input checked="" type="radio"/> without address
Heterogen	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Logging	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No

Click "back" to show details

After execution, you can identify the IDoc-Number and associated records for each table




Table	Records
T052	11
T052U	16
TVZB	9
TVZBT	18


  

IDoc-Number	Receiver	MessageType	IDocType	Table	Data_30_Characters
0000000000108001	IH2400	/ITG/GENERIC	/ITG/GENERIC02	T052	10000010000000000 0.000 000 0.

### 3.2.3.3 Snapshot Mode

The Snapshot mode offers the comparison, deletion and activation of data, as well as the creation of backups before activating data.

Choose the Configuration Group and choose "Snapshot". For options choose e.g. "Logging" and "Detail List". Then click execute.



RDH: ReferenceDataHarmonization - Send Objects

ObjectSelection

Table(s)	TFKB
View(s)	
Objectgroup(s)	FUNCTIONAREA

ALE / WebService

MessageType	/ITG/GENERIC
Logical System	IH2400
Port for WebService	

Mode

Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input checked="" type="radio"/> SnapShot	<input type="radio"/> Transport
----------	------------------------------	------------------------------	---	---------------------------------

Options

Scope	<input type="radio"/> with address	<input checked="" type="radio"/> without address
Heterogen	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Logging	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No

Key fields will be shown

SAP ProductivRun / Show Keys for table

Table Name	Short Description	Number
Table Name		
T002	Language Keys (Component BC-I18)	
T002	#	# S 0 VI
T002	0	0 S 0 SR
T002	1	1 D 0 ZH
T002	2	2 M 0 TH
T002	3	3 D 0 KO
T002	4	4 S 0 RO
T002	5	5 S 0 SL
T002	6	6 S 0 HR
T002	7	7 S 4 MS
T002	8	8 S 0 UK
T002	9	9 S 0 ET
T002	A	A L 0 AR
T002	B	B L 0 HE

Click "back" and verify that all data records have been added to one message (IDoc or Web-Service).

RDH: Customizing Harmonization - Send/Activate Objects

Snapshot: T002	47	0	Indexid = T002102138		
Snapshot: TFKB	20	0	Indexid = TFKB102138		
Snapshot: TFKBT	40	0	Indexid = TFKBT102138		
<b>Idoc-Number</b>	Receiver	MessageType	<b>IdocType</b>	Table	Data_30_Characters
000000000109001	IH2400	/ITG/GENERIC	/ITG/GENERIC02	/ITR/SNAPSHOT_C	100ZZT002102138 0

### 3.2.3.4 Transport Mode

The Transport Mode creates a transport with entries. You can easily track and manage the data replication through the assigned transport ID.

You can

- Create a transport with compressed data
- Create a transport with readable data
- Add data to an existing transport

#### Create a transport with compressed data:

Choose the Configuration Group in the "Objectgroup" field, enter the tables and the receiver system. Choose mode "Transport". For options choose "Logging" and "DetailList" and for TR Mode "SnapShot". Then click Execute.

**SAP RDH: ReferenceDataHarmonization - Send Objects**

ObjectSelection

Table(s)	TVBUR	to	
View(s)		to	
Objectgroup(s)	SALESOFFICE	to	

ALE / WebService

MessageType	/ITG/GENERATE
Logical System	IH1400
Port for WebService	
Transport request	

Mode

Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input type="radio"/> SnapShot	<input checked="" type="radio"/> Transport
----------	------------------------------	------------------------------	--------------------------------	--

Options


Scope	<input checked="" type="radio"/> with address	<input type="radio"/> without address
Heterogen	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Logging	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Override	<input type="radio"/> Yes	<input checked="" type="radio"/> No
TR-Mode	<input type="radio"/> R3TR/TABU	<input checked="" type="radio"/> SnapShot

Click back to see the ID of the transport.

**RDH: Customizing Harmonization - Send/Activate Objects**

Snapshot: TVBUR	Indexid = TVBUR121321
DB-Cnt	Addr-Cnt
8	6
Snapshot: TVKBT	Indexid = TVKBT121321
DB-Cnt	Addr-Cnt
11	0
Snapshot: TVKGR	Indexid = TVKGR121321
DB-Cnt	Addr-Cnt
22	0
IH1K901795	

Use Transaction SE09 to access the transport. The data is shown in a compressed form.



### Create a transport with readable data:

To get the transport in a readable form, select TR Mode R3TR/TABU when sending as TR-Mode.


Options	
Scope	<input checked="" type="radio"/> with address <input type="radio"/> without address
Heterogen	<input checked="" type="radio"/> Yes <input type="radio"/> No
Logging	<input checked="" type="radio"/> Yes <input type="radio"/> No
Changes	<input type="radio"/> Yes <input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes <input checked="" type="radio"/> No
Test	<input type="radio"/> Yes <input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes <input type="radio"/> No
Override	<input type="radio"/> Yes <input checked="" type="radio"/> No
TR-Mode	<input checked="" type="radio"/> R3TR/TABU <input type="radio"/> SnapShot

### Send Data

RDH: Customizing Harmonization – Send/Activate Objects


IH1K901804	Table: TVBUR	Records: 8
	Table: TVKBT	Records: 11
	Table: TVKGR	Records: 22

Check the transport via SE09. The details are now in a readable form




### Add data to an existing transport:

Choose Transport Mode and select your transport in field "Transport Request". You can add it as readable or compressed data.



The image shows two SAP application windows. The left window is titled 'ALE / WebService' and contains fields for 'MessageType' (set to '/ITG/GENERIC'), 'Logical System' (set to 'IH1400'), and 'Transport request' (which is highlighted with a red box). Below these are 'Mode' options (Transfer, Single, Bundle, SnapShot) and 'Options' (Scope: with address, without address; Address: Yes, No). The right window is titled 'Objekte analysieren...' and shows a tree structure of objects. It includes 'Modifiable' (Workbench Request, IH1K901795, SATTLERU, CustSync-), 'Customizing' (Customizing Request, IH1K901804; 100, SATTLERU, test), and other entries like IH1K901802 100 and IH1K901800 100. The 'Customizing' node and its sub-entries are also highlighted with a red box.

The SAP transport can be imported into a receiving system by uploading the corresponding transport files to the target system, appending them to the import queue in transaction STMS (Transport Management System), and then starting the transport request via the "truck icon" to import the changes



The image shows the 'SAP Transport Organizer: Requests' interface. The title bar is 'SAP Transport Organizer: Requests'. Below it is a toolbar with various icons, including a truck icon which is highlighted with a red box. The main area is titled 'Change Requests Involving User IT\_ALL\_02 ( IT\_ALL\_02 )'. It shows a tree structure of change requests. One request under '100 Itego' is highlighted with a red box: 'Workbench request' (VH1) under 'Modifiable' (IH2K900300, IT\_ALL\_02, CustSync-> IT\_ALL\_02 20231106 131115).

### 3.2.3.5 *Online Selection*

The Online Selection is designed to provide manual control over the data to be replicated. When this option is activated, users can interactively select specific entries and fields for data transfer, instead of sending the complete table. Choose the receiver system, Snapshot or Transport and click OnlineSel.

ObjectSelection																					
Table(s)	<input type="text"/>	to	<input type="text"/> <input type="button" value="→"/>																		
View(s)	<input type="text"/>	to	<input type="text"/> <input type="button" value="→"/>																		
Objectgroup(s)	<input type="text"/>	to	<input type="text"/> <input type="button" value="→"/>																		
RDH: Configuration Group																					
<b>ALE / WebService</b> <table border="1"> <tr> <td>MessageType</td> <td><input type="text" value="/TTG/GENFRTC"/></td> </tr> <tr> <td>Logical System</td> <td><input style="border: 2px solid red;" type="text" value="IH1400"/></td> </tr> <tr> <td>Port for WebService</td> <td><input type="text"/></td> </tr> </table>				MessageType	<input type="text" value="/TTG/GENFRTC"/>	Logical System	<input style="border: 2px solid red;" type="text" value="IH1400"/>	Port for WebService	<input type="text"/>												
MessageType	<input type="text" value="/TTG/GENFRTC"/>																				
Logical System	<input style="border: 2px solid red;" type="text" value="IH1400"/>																				
Port for WebService	<input type="text"/>																				
<b>Mode</b> <table border="1"> <tr> <td>Transfer</td> <td><input type="radio"/> Single</td> <td><input type="radio"/> Bundle</td> <td><input checked="" type="radio"/> SnapShot</td> <td><input type="radio"/> Transport</td> </tr> </table>				Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input checked="" type="radio"/> SnapShot	<input type="radio"/> Transport													
Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input checked="" type="radio"/> SnapShot	<input type="radio"/> Transport																	
<b>Options</b> <table border="1"> <tr> <td>Scope</td> <td><input checked="" type="radio"/> with address</td> <td><input type="radio"/> without address</td> </tr> <tr> <td>Heterogen</td> <td><input checked="" type="radio"/> Yes</td> <td><input type="radio"/> No</td> </tr> <tr> <td>Logging</td> <td><input type="radio"/> Yes</td> <td><input checked="" type="radio"/> No</td> </tr> <tr> <td>Changes</td> <td><input type="radio"/> Yes</td> <td><input checked="" type="radio"/> No</td> </tr> <tr> <td>OnlineSele</td> <td><input checked="" type="radio"/> Yes</td> <td><input type="radio"/> No</td> </tr> <tr> <td>Test</td> <td><input type="radio"/> Yes</td> <td><input checked="" type="radio"/> No</td> </tr> </table>				Scope	<input checked="" type="radio"/> with address	<input type="radio"/> without address	Heterogen	<input checked="" type="radio"/> Yes	<input type="radio"/> No	Logging	<input type="radio"/> Yes	<input checked="" type="radio"/> No	Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No	OnlineSele	<input checked="" type="radio"/> Yes	<input type="radio"/> No	Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Scope	<input checked="" type="radio"/> with address	<input type="radio"/> without address																			
Heterogen	<input checked="" type="radio"/> Yes	<input type="radio"/> No																			
Logging	<input type="radio"/> Yes	<input checked="" type="radio"/> No																			
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No																			
OnlineSele	<input checked="" type="radio"/> Yes	<input type="radio"/> No																			
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No																			

## Choose the table

CHOOSE THE TABLE

**SAP RDH: select TableEntries for Customizing-Harmonization**

Object Selection and return

Table	<input type="text" value="TVBUR"/>	
-------	------------------------------------	--


Select the entry you want to choose with left click and "Object Selection and return"

The screenshot shows the Microsoft Word ribbon with the 'Start' tab selected. A context menu is open over a table cell, listing the following options: 'Copy Text', 'Insert with Overwrite', 'Details', 'Optimize Width', 'Unfreeze Columns', 'Spreadsheet...', and 'Object Selection and return'. The 'Object Selection and return' option is highlighted with a red box.

Choose Online Selection to see if the entries are there.

**SAP RDH: ReferenceDataHarmonization – Send Objects**

The chosen entry should be shown.



RDH: Reference

RDH: Customizing Harmonization – Send/Activate Objects

TVBUR  
100ZU


Choose "DetailList" and press execute. Check the List to see if the right entry was chosen

Table Name	Short Description	Number
Table Name		
TVBUR	Organizational Unit: Sales Offices	
TVBUR	100ZU	100 ZU 0000000782 SATTLERU

In the receiver system check if the entries are shown.

<input type="checkbox"/> ->IH110020251020144239	<input type="checkbox"/> TVBUR	1	1	Organizational Unit: Sales Offices	TVBUR14423
<input type="checkbox"/> ->IH140020251010091205	<input type="checkbox"/> TVKBT	1	1	Organizational Unit: Sales Offices: Texts	TVKBT14423
<input type="checkbox"/> ->IH140020251010091205	<input type="checkbox"/> T003	52	52	Document Types	T003091205
<input type="checkbox"/> SOff.	Address	Created by	Adr.text	HeaderText	Footer txt
<input type="checkbox"/> ZU	782	SATTLERU			Greeting
					Text SDS
					Hide in F4

If you would like to choose specific fields, choose "Options"



SAP RDH: select TableEntries for Customizing-Harmonization

Object Selection and return

Table: TVBUR

Options

<input checked="" type="checkbox"/> VKBUR	Sales Office
<input checked="" type="checkbox"/> ADRNR	Address
<input type="checkbox"/> ERNAM	User Creating Record
<input type="checkbox"/> TXNAM_ADR	Text name for form text module
<input type="checkbox"/> TXNAM_KOP	Text name for form text module
<input type="checkbox"/> TXNAM_FUS	Text name for formula text mod
<input type="checkbox"/> TXNAM_GRU	Text name for form text module
<input type="checkbox"/> TXNAM_SDB	Text names for layout-set modu
<input type="checkbox"/> HIDE	Customization of SD Input Help

Confirm with Enter, choose the entries to send and go back to execute. Check the Online-Selection

**SAP RDH: ReferenceDataHarmonization – Send Objects**

Online-Selection

RDH: Customizing Harmonization – Send/Activate Objects

TVBUR  
100U1

Enter your receiver system and Option “DetailList” and send the data

**ALE / WebService**

MessageType	/ITG/GENERIC
Logical System	IH1400
Port for WebService	

**Mode**

Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input checked="" type="radio"/> SnapShot
----------	------------------------------	------------------------------	---


**Options**

Scope	<input checked="" type="radio"/> with address	<input type="radio"/> without address
Heterogen	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Logging	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No


Table Name	Short Description	Number
Table Name		
TVBUR	Organizational Unit: Sales Offices	
TVBUR	100U1	100 U1 0000000524

### 3.2.4 Send Mode – Monitoring


The Monitoring functionality is essential to track and manage the associated messages (e.g. IDocs). In Send mode select the “Monitoring” tab.



In the Replication Monitor you can see the IDoc for the data which has been replicated




To see details click the IDoc number and check the data records.



### 3.3 Receive Mode

### 3.3.1 Receive Mode – Logging

Logging allows you to review the logs and details for messages (e.g. IDocs) processed in the receiver system. In Receiver mode select the tab "Logging"




Choose the time and date when the IDoc was processed.

**SAP Display logs ( 2 )**

?	Technical Information	i						
<b>SAP Display logs ( 2 )</b>								
Date/Time/User	Numb. External ID	Object text	Subobject Text	Transactio...	Program	Mode	Log Number	
21.10.2023 13:51:04 IT_ALL_(5	/ITR/SNAPSHOT_	RDM-StagingLo...	/ITR/CUSTSYNC	/ITR/RDH...	/ITR/SEND...	Dialog proc...	000000000000000208...	
21.10.2023 14:01:11 IT_ALL_(6	/ITR/SNAPSHOT_	RDM-StagingLo...	/ITR/CUSTSYNC	/ITR/RDH...	/ITR/SEND...	Dialog proc...	000000000000000208...	

### 3.3.2 Receive Mode – Activation

The activation option allows to activate Snapshots. This step involves a detailed overview, comparison, deletion of snapshots, backup creation, activation flag setting, and the final activation of Snapshots. Select the tab "Activate" in Receiver mode.



An overview of all Snapshots is displayed

**RDH: Show/Activate SnapShot(s)**


Choice									
IndexId	<input type="text"/>	to	<input type="text"/>	<input type="button"/>					
Version	<input type="text"/>	to	<input type="text"/>	<input type="button"/>					
Table	<input type="text"/>	to	<input type="text"/>	<input type="button"/>					
Date	<input type="text"/> 08.10.2023	to	<input type="text"/> 22.10.2023	<input type="button"/>					

Results: 0006

ID	Table	DB-Entr.	AD-Entries	Short Description	MainIndex	AddrIndex	User	Program	Current Date	Time	SAP
->IH210020231022102138	T002	47		Language Keys (Component BC-I18)	T002102138		IT_ALL_02	RDH	22.10.2023	10:21:38	IH2
	TFKB	20		Functional areas	TFKB102138		IT_ALL_02	RDH	22.10.2023	10:21:38	IH2
	TFKBT	40		Name of the functional areas	TFKBT102138		IT_ALL_02	RDH	22.10.2023	10:21:38	IH2
->IH210020231022102707	T002	47		Language Keys (Component BC-I18)	T002102707		IT_ALL_02	RDH	22.10.2023	10:27:07	IH2
	TFKB	20		Functional areas	TFKB102707		IT_ALL_02	RDH	22.10.2023	10:27:07	IH2
	TFKBT	40		Name of the functional areas	TFKBT102707		IT_ALL_02	RDH	22.10.2023	10:27:07	IH2

### 3.3.2.1 Compare

To compare differences between Sender- and Receiver left click and select "Compare (Overview)".




DB\_Only: indicates records existing only in the receiver system.

Ind\_Only: indicates records existing only in the sender system.

Diff: indicates records with different content between the systems.

Program	Current Date	Time	SAP System	Mandt	DB-Only	Ind_Only	Diff	Ident	All-DB	Act-User	Act-Date	Act-Time
RDH	22.10.2023	10:21:38	IH2	100							00:00:00	
RDH	22.10.2023	10:21:38	IH2	100							00:00:00	
RDH	22.10.2023	10:21:38	IH2	100							00:00:00	
RDH	22.10.2023	10:27:07	IH2	100			47	47			00:00:00	
RDH	22.10.2023	10:27:07	IH2	100			20	20			00:00:00	
RDH	22.10.2023	10:27:07	IH2	100			40	40			00:00:00	


You can compare individual table content with "Compare".



The numbers indicate where the differences are or if the content is only in one system or is identical.

RDH: Show/Activate SnapShot(s)		1
<b>Differences (1=DB only,2=IND-only,3=DIFF,4=IDEN)</b>		
Select Row ( 3=DIIF ) shows Details!		
0001 0005 0002 0031		
1 xxxxEKW04		
2	xxxxDKW01	
2	xxxxDKW02	
2	xxxxDKW03	
2	xxxxEKW02	
2	xxxxEKW03	
3	xxxxE0100	
3	xxxxEKW01	
4	xxxxD0001	
4	xxxxD0002	
4	xxxxD0003	
4	xxxxD0004	
4	xxxxD0100	
4	xxxxD0300	
4	xxxxD0400	
4	xxxxD0500	
4	xxxxD0980	


You can show all differences by selecting "All differences".



Records selected: 00000017							
El	Ta...	Key	Field	Short Description	Long Field Label	SnapShotValue	DBValue
	TFKB	xxxKW02	FKBER	Functional Area	Functional Area	KW02	KW01
		xxxKW03	FKBER	Functional Area	Functional Area	KW03	KW04
		xxxKW04	FKBER	Functional Area	Functional Area	KW02	KW04
	TFKBT	xxxDKW01	FKBER	Functional Area	Functional Area	KW01	0980
			FKBTX	Name of the functional area	FunctArea text	Management	Kalk. Kosten
		xxxDKW02	FKBER	Functional Area	Functional Area	KW02	PT01
			FKBTX	Name of the functional area	FunctArea text	Produktion	Verkaufs- und Servicekost
		xxxDKW03	FKBER	Functional Area	Functional Area	KW03	PT02
			FKBTX	Name of the functional area	FunctArea text	Steuer Sonderergebnis	Vertriebskosten
		xxxE0100	FKBTX	Name of the functional area	FunctArea text	Production-Support	Production
		xxxEKW01	FKBTX	Name of the functional area	FunctArea text	Management	Sales department
		xxxEKW02	FKBER	Functional Area	Functional Area	KW02	PT02
			FKBTX	Name of the functional area	FunctArea text	Production	Sales costs
		xxxEKW03	FKBER	Functional Area	Functional Area	KW03	PT03
			FKBTX	Name of the functional area	FunctArea text	Administration	Administration Costs
		xxxEKW04	FKBER	Functional Area	Functional Area	0500	KW04
			FKBTX	Name of the functional area	FunctArea text	Research & Development	Trade


### 3.3.2.2 Delete

The delete option allows to remove unwanted Snapshots. You can delete Snapshots with left click and "Delete".



### 3.3.2.3 Save before Activate

It is possible to create a backup Snapshot before the activation, for this select "Save Before Activate".




The backup Snapshot is saved.

->IH210020231022102707	T002	47	Language Keys (Component BC-I18)	T002102707	IT_ALL
	TFKB	20	Functional areas	TFKB102707	IT_ALL
	TFKBT	40	Name of the functional areas	TFKBT102707	IT_ALL
->SAVECO20231022105844	T002	47	Language Keys (Component BC-I18)	T002105844	IT_ALL
	TFKB	20	Functional areas	TFKB105844	IT_ALL
	TFKBT	40	Name of the functional areas	TFKBT105844	IT_ALL

### 3.3.2.4 Set Activation Flag

The activation flag designed to provide users a visual indicator for status of Snapshots, in order to categorize and differentiate between activated and non-activated Snapshots. You can set an activation flag by selecting "Set Active-Flags".




Now you can see the activation flags.

Er	Act-Date	Act-Time	Act-Flag
	00:00:00		<input type="checkbox"/>
	00:00:00		<input type="checkbox"/>
	00:00:00		<input type="checkbox"/>
	00:00:00		<input checked="" type="checkbox"/>
	00:00:00		<input checked="" type="checkbox"/>
	00:00:00		<input checked="" type="checkbox"/>
	00:00:00		<input type="checkbox"/>
	00:00:00		<input type="checkbox"/>
	00:00:00		<input type="checkbox"/>

### 3.3.2.5 Activate

For activation select "Activate (all)".



Activated Snapshots will be displayed:

RDH: Show/Activate SnapShot(s)			
RDH: Show/Activate SnapShot(s)			
T002	activated:	47	->IH210020231022102707 T002102707
TFKB	activated:	20	->IH210020231022102707 TFKB102707
TFKBT	activated:	40	->IH210020231022102707 TFKBT102707

After confirming you can see the activation date and time.

ndt	Act-User	Act-Date	Act-Time	Fore...
0			00:00:00	
0			00:00:00	
0			00:00:00	
0	IT_ALL_02	22.10.2023	11:06:22	✓
0	IT_ALL_02	22.10.2023	11:06:22	✓
0	IT_ALL_02	22.10.2023	11:06:22	✓
0			00:00:00	
0			00:00:00	
0			00:00:00	

## 3.4 Expert Mode

### 3.4.1 Expert Mode – Business Objects

The "Business Objects" option allows to create custom business objects.

Click the Business Objects button in Expert mode

**SAP RDH-Cockpit: Expertmode**

 Expert

#### Groups and Foreign Keys

 Configuration Groups

 Foreign Keys

 I

 Business Objects

 Recreate Foreign Keys

Switch to edit mode and click new Entries

**SAP Change View "RDH: BusinessObjects": Overview**



New Entries



#### RDH: BusinessObjects

Object	Table Name	Short Description
ACCOUNTS	SKA1	G/L account A-Seg
ACCOUNTS	SKAT	G/L account TXT
ACCOUNTS	SKB1	G/L account B-Seg
BUSINESSPARTNER	ADRC	Addresses (Business Address Services)

Enter the name for the new Business Object and the corresponding table, as well as a description. Then confirm and save



RDH: BusinessObjects		
Object	Table Name	Short Description
Functional AreaTFKB	FAGL_011SC	Functional Area
Functional AreaTFKBT	FAGL_011TC	Functional Area TxT

After saving the Business Object is created




RDH: BusinessObjects		
Object	Table Name	Short Description
FRS	FAGL_011SC	Balance sheet structure
FRS	FAGL_011TC	Balance sheet structure
FRS	FAGL_011VC	Balance sheet structure
FRS	FAGL_011ZC	Balance sheet structure
FRS	T011	Balance sheet structure
FRS	T011T	Balance sheet structure
FUNCTIONAL AREA	TFKB	Functional Area
FUNCTIONAL AREA	TFKBT	Functional Area TxT
KONTRAKT	EKBE	Purchasing document history
KONTRAKT	EKET	Scheduling agreement schedule lines

### 3.4.2 Expert Mode – Foreign Keys

The Foreign Keys can be assigned to the Configuration Groups, which ensures that related data is handled consistently during data replication processes. While it can simplify management, it may add complexity to the configuration, especially if there are many interdependencies between tables, but it is generally advisable to include key tables that are closely related and need to be replicated together in order to maintain data integrity.

In Expert mode select “Foreign Keys”



## Search for your Business Object

SAP RDH: ForeignKeys

BusinessObject Table

FUNCTIONAL AREA

Records selected : 00000006

Object	Table	Field name	Short Description	Check table	Short Description	Field Name
FUNCTIONA...	TFKB	FNSUB1	Substring 1 of Functional Area	FMMDFNSUB1	Value of Substring 1 of Functional Area	FNSUB1
FUNCTIONA...	TFKB	FNSUB2	Substring 2 of Functional Area	FMMDFNSUB2	Value of Substring 2 of Functional Area	FNSUB2
FUNCTIONA...	TFKB	FNSUB3	Substring 3 of Functional Area	FMMDFNSUB3	Value of Substring 3 of Functional Area	FNSUB3
FUNCTIONA...	TFKB	STR_ID	Master Data Subdivision ID	FMMDSTRID	Define Subdivision ID of FM Master Data	STR_ID
FUNCTIONA...	TFKB	FKBER	Functional Area	TFKB	Functional areas	FKBER
FUNCTIONA...	TFKBT	SPRAS	Language Key	T002	Language Keys (Component BC-I18)	SPRAS

Select the entries and click "Include in RDH Groups"

Records selected : 00000006

FUNCTIONAL AREA

Records selected : 00000006

Object	Table	Field name	Short Description	Check table	Short Description	Field Name
FUNCTIONA...	TFKB	FNSUB1	Substring 1 of Functional Area	FMMDFNSUB1	Value of Substring 1 of Functional Area	FNSUB1
FUNCTIONA...	TFKB	FNSUB2	Substring 2 of Functional Area	FMMDFNSUB2	Value of Substring 2 of Functional Area	FNSUB2
FUNCTIONA...	TFKB	FNSUB3	Substring 3 of Functional Area	FMMDFNSUB3	Value of Substring 3 of Functional Area	FNSUB3
FUNCTIONA...	TFKB	STR_ID	Master Data Subdivision ID	FMMDSTRID	Define Subdivision ID of FM Master Data	STR_ID
FUNCTIONA...	TFKB	FKBER	Functional Area	TFKB	Functional areas	FKBER
FUNCTIONA...	TFKBT	SPRAS	Language Key	T002	Language Keys (Component BC-I18)	SPRAS

Choose the Configuration Group

Records selected : 00000006

FUNCTIONAL AREA

Group Selection

- CUSTOMER\_SCY
- FB-TEST-GR2
- CURRENCY
- LGORTE
- MATTYP
- WERKSTOFF
- FUNCTIONAREA**
- RDM-OBJECTS**
- RDM\_OBJECTS
- S02\_BNKA

Check the Configuration Group and verify that the foreign key tables have been added to the

## Configuration Group

SAP Change View "RefData Harmonization - Objects": Overview

Configuration G.	Table Name	Line	A	Object key
RefData Harmonization - G	RefData Harmonization			
	FUNCTIONAREA FMMDFNSUB1	1	<input checked="" type="checkbox"/>	100*
	FUNCTIONAREA FMMDFNSUB2	1	<input checked="" type="checkbox"/>	100*
	FUNCTIONAREA FMMDFNSUB3	1	<input checked="" type="checkbox"/>	100*
	FUNCTIONAREA FMMDSTRID	1	<input checked="" type="checkbox"/>	100*
	FUNCTIONAREA T002	1	<input checked="" type="checkbox"/>	*
	FUNCTIONAREA TFKB	1	<input checked="" type="checkbox"/>	100*
	FUNCTIONAREA TFKBT	1	<input checked="" type="checkbox"/>	100**

### 3.4.3 Expert Mode – Recreate Foreign Keys

Recreating foreign keys is important after creating a Business Object. It ensures that dependent tables, linked with foreign keys and associated with specified tables in Configuration Groups, are accurately linked to the Business Object.

In Expert mode click the tab "Recreate Foreign Keys"

Groups and Foreign Keys

Configuration Groups      Foreign Keys      Business Objects      Recreate Foreign Keys

Choose the Business Object for which a foreign key table should be created and click execute

SAP BusinessObject

Object	Short Description
DEBITOR	Customer master (general part EC tax numbers)
DEBITOR	Customer master (general part)
DEBITOR	Customer master credit management: central data
DEBITOR	Customer payment history
DEBITOR	Return structure for address
FRS	Balance sheet structure
FUNCTIONAL AREA	Functional Area
FUNCTIONAL AREA	Functional Area Txt
KONTRAKT	Account assignment in purchasing document
KONTRAKT	Purchasing document header

The created list shows related tables which supports the creation of a new Business Object by ensuring that dependent tables with foreign keys are searched, harmonized, and connected, maintaining the integrity and consistency of the entire object, especially when data is replicated across various systems.

**SAP BusinessObject**

BusinessObject			
TFKB	FNSUB1	Substring 1 of Functional Area	FMMDFNSUB1
TFKB	FNSUB1	Substring 1 of Functional Area	FMMDFNSUB1
TFKB	FNSUB2	Substring 2 of Functional Area	FMMDFNSUB2
TFKB	FNSUB2	Substring 2 of Functional Area	FMMDFNSUB2
TFKB	FNSUB3	Substring 3 of Functional Area	FMMDFNSUB3
TFKB	FNSUB3	Substring 3 of Functional Area	FMMDFNSUB3
TFKB	STR_ID	Master Data Subdivision ID	FMMDFSTRID
TFKB	STR_ID	Master Data Subdivision ID	FMMDFSTRID
TFKBT	FKBER	Functional Area	TFKB
TFKBT	SPRAS	Language Key	T002

### 3.4.4 Expert Mode – Field Reduction

Field Reduction is designed to customize and control the reduction of specific fields in the data replication process. It ensures that content is not overwritten in the receiving system, preserving maintained values during the data replication. Select Expert Mode and then click Field Reduction (or use transaction /ITG/REDUCE\_GENIDOC).

Settings

**Field Reduction** (highlighted with a red box)

Enhancements

Overwrite Protection

Select the table of the business object (in this case document type) and the target (receiving) system for the reduction. If no target system is chosen, the reduction applies to all systems.

GenericIdoc Reduction

Table: T003

Target System: IH2400

Choose the fields that should be reduced and click Deselect. Save your selection.

Segment T003: Fields	
Ad	Status Field
<input type="checkbox"/>	MANDT Client
<input checked="" type="checkbox"/>	BLART Document Type
<input type="checkbox"/>	NUMKR Number Range
<input type="checkbox"/>	KOARS Account Types
<input type="checkbox"/>	STBLA Reverse DocumentType
<input type="checkbox"/>	XNETB
<input type="checkbox"/>	XRVUP SAP Billing Document
<input type="checkbox"/>	XSYBL Batch Input Only
<input type="checkbox"/>	XVORK Init.Acct Assignment
<input type="checkbox"/>	XXKPR Only One Customer/Vendor Allowed?
<input type="checkbox"/>	XGSUB Inter-Company
<input type="checkbox"/>	XMGES Enter Trading Part.
<input type="checkbox"/>	BRGRU Authorization Group
<input type="checkbox"/>	RECID Debit Rec.Indicator
<input type="checkbox"/>	RECIC Rec.Indicator Credit
<input type="checkbox"/>	XMTXT Document Header Text
<input type="checkbox"/>	XMREF Reference Number
<input type="checkbox"/>	XNGBK Doc.Type for Subseq.Adjustment
<input type="checkbox"/>	KURST Exchange Rate Type for FC Documents
<input type="checkbox"/>	XNEGP Negative Postings Permitted
<input type="checkbox"/>	XKQAA
<input type="checkbox"/>	XKOAD
<input type="checkbox"/>	XKOAK
<input type="checkbox"/>	XKOAM
<input type="checkbox"/>	XKOAS
<input type="checkbox"/>	XNMRL Official document numbering
<input type="checkbox"/>	XAUSG Self-issued document
<input type="checkbox"/>	XDTCR Check Date
<input type="checkbox"/>	BLKLS Document Class
<input type="checkbox"/>	XROLLUP Rollup
<input type="checkbox"/>	XPLAN Planning
<input type="checkbox"/>	XALLOCAT Act.Allocation

Segment T003: Fields			
Ad	Status	Field	Text
<input checked="" type="checkbox"/>		MANDT	Client
<input checked="" type="checkbox"/>		BLART	Document Type
<input type="checkbox"/>		NUMKR	Number Range
<input type="checkbox"/>		KOARS	Account Types
<input type="checkbox"/>		STBLA	Reverse DocumentType

To validate the field reduction, replicate an object (in this example document type) and check the monitoring. For the number range (NUMKR) the reduction was successful and is marked with a slash which informs the receiving system to preserve the local value of the field.

IDoc Display: 000000000096005

Segments with Errors		Additional information	Short Technical Information	
▼	📁 IDoc 000000000096005		Direction	2 Inbox
▪	Control record	Total number: 000041	Current Status	53 OOB
▼	📁 Data records	Segment 000001	Basic type	/ITG/GENERIC02
✓	📄 /ITG/HEADER	Segment 000002	Extension	
▪	📄 /ITG/POSITIONS	Segment 000003	Message Type	/ITG/GENERIC
▪	📄 /ITG/POSITIONS	Segment 000004	Partner No.	IH2100
▪	📄 /ITG/POSITIONS	Segment 000005	Partn.Type	LS
▪	📄 /ITG/POSITIONS	Segment 000006	Port	SAPIH2
▪	📄 /ITG/POSITIONS	Segment 000007		
▪	📄 /ITG/POSITIONS	Segment 000008		
▪	📄 /ITG/POSITIONS	Segment 000009		
▪	📄 /ITG/POSITIONS	Segment 000010		
▪	📄 /ITG/POSITIONS	Segment 000011		
▪	📄 /ITG/POSITIONS	Segment 000012		
▪	📄 /ITG/POSITIONS	Segment 000013		
▪	📄 /ITG/POSITIONS	Segment 000014		
▪	📄 /ITG/POSITIONS	Segment 000015		
▪	📄 /ITG/POSITIONS	Segment 000016		

### 3.4.5 Expert Mode – Overwrite Protection


In the receiving system, fields can additionally be protected against overwriting during a data replication in Snapshot mode. Fields which are deactivated are not overwritten in the receiver system. For this select the Overwrite Protection in Expert Mode on your receiver system.



Choose the table for which the table content wants to be protected in the receiver system.




Choose the field you want to protect and click Deselect.



Status	Field	Text
<input checked="" type="checkbox"/>	MANDT	Client
<input checked="" type="checkbox"/>	FKBER	Functional Area
<input checked="" type="checkbox"/>	AUTHGRP	Authorization Group
<input type="checkbox"/>	STR_ID	Master Data Subdivision ID
<input type="checkbox"/>	FNSUB1	Functional Area Substring 1
<input type="checkbox"/>	FNSUB2	Functional Area Substring 2
<input type="checkbox"/>	FNSUB3	Functional Area Substring 3
<input type="checkbox"/>	CREATED_BY	Created By
<input type="checkbox"/>	CREATED_ON	Entered On
<input type="checkbox"/>	CREATED_AT	Entered at
<input type="checkbox"/>	MODIFIED_BY	Changed By
<input type="checkbox"/>	MODIFIED_ON	Changed On
<input type="checkbox"/>	MODIFIED_AT	Changed at
<input type="checkbox"/>	DATAB	Valid From
<input type="checkbox"/>	DATBIS	Valid To
<input type="checkbox"/>	DATE_EXP	Expiration Date

After saving it is marked as deselected



Status	Field	Text
<input checked="" type="checkbox"/>	MANDT	Client
<input checked="" type="checkbox"/>	FKBER	Functional Area
<input type="checkbox"/>	AUTHGRP	Authorization Group
<input type="checkbox"/>	STR_ID	Master Data Subdivision ID
<input type="checkbox"/>	FNSUB1	Functional Area Substring 1
<input type="checkbox"/>	FNSUB2	Functional Area Substring 2
<input type="checkbox"/>	FNSUB3	Functional Area Substring 3

To verify choose Send in Send Mode.

Send, Check and Activate

 Send

 Monitoring

 i

 Check

 Logging

## Create a Snapshot

   IdocReduction
Show Protocols
Online-Selection

ObjectSelection

Table(s)	TFKB	to	[ ] 
View(s)		to	[ ] 
Objectgroup(s)	FUNCTIONAREA	to	[ ] 

ALE / WebService

MessageType	/ITG/GENERIC
Logical System	IH2400
Port for WebService	

Mode

Transfer	<input type="radio"/> Single	<input type="radio"/> Bundle	<input checked="" type="radio"/> SnapShot	<input type="radio"/> Transport
----------	------------------------------	------------------------------	---	---------------------------------

Options

Scope	<input type="radio"/> with address	<input checked="" type="radio"/> without address
Heterogen	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Logging	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No

The Authorization Group is filled with A001 and sent to the receiver system.

SAP ProductivRun / Show Keys for table

        >|

Table Name	Short Description	Number
Table Name		
TFKB	Functional areas	
TFKB	100KW01	100 KW01 
TFKBT	Name of the functional areas	
TFKBT	100DKW01	100 D KW01
TFKBT	100EKW01	100 E KW01
		Management
		Management _Support

RDH: Customizing Harmonization – Send/Activate Objects

Snapshot: TFKB Indexid = TFKB122426

Snapshot: TFKBT Indexid = TFKBT122426

Idoc-Number	Receiver	MessageType	IdocType
000000000115001	IH2400	/ITG/GENERIC	/ITG/GENERIC02


Switch to Receiver mode on your receiver system and select **Activate** to display the Snapshot.

### Send, Check and Activate



Left click and select "All differences".


**SAP** RDH: Show/Activate SnapShot(s)



Here the differences in the Snapshot between sender and receiver system are shown.

Records selected: 00000001

To activate set the Active Flag and select "Activate (all)":



RDH: Show/Activate Snapshot(s)

TFKB	activated:	1	→IH210020231106122426 TFKB122426
TFKBT	activated:	2	→IH210020231106122426 TFKBT122426

You can compare the tables in the sender (left) and receiver system (right) and can see that the value was not overwritten.

**SAP Data Browser: Table TFKB Select Entries**

Table: TFKB  
Displayed Fields: 17 of 17  
Fixed Columns:

MANDT	FKBER	AUTHGRP	STR_ID	FNSUB1
100	0001			
100	0002			
100	0003			
100	0004			
100	0100			
100	0300			
100	0400			
100	0500			
100	0980			
100	KW01	A001		
100	KW02			
100	KW03			

**SAP Data Browser: Table TFKB Select Entries**

Table: TFKB  
Displayed Fields: 17 of 17  
Fixed Columns:

MANDT	FKBER	AUTHGRP	STR_ID	FNSUB1
400	0001			
400	0002			
400	0003			
400	0004			
400	0100			
400	0300			
400	0400			
400	0500			
400	0980			
400	KW01	X000		
400	KW02			
400	KW03			

### 3.4.6 Expert Mode – Filter Groups

Filter Groups are designed to control and limit the scope of data transferred between systems. By defining filter criteria for one or multiple tables, only records meeting the specified conditions are included in the data transmission.

In the RDH Cockpit in Expert Mode select Filter Groups.



Enter a new Name for the Filter Group and select Create/Maintain FilterGroup.



Enter a new Filter Group



### 3.4.6.1 Testmode


Go back enter the Table and choose "Testmode".



Filter for one or several fields. In this case only sales offices that begin with U.



Since test mode was selected the chosen entries are shown without saving. The filter is not configured yet.



### 3.4.6.2 Create Filter group

Repeat the steps without test mode.



The screenshot shows the SAP Filtergroup(s) dialog. On the left, there is a tree view under 'Organizational Unit: Sales Offices' with several items listed. On the right, there is a 'Create/Maintain FilterGroup(s)' form with a 'Sales Office' field and a 'Save' button. The 'Save' button is highlighted with a red box.

After execution the filter is saved.

### 3.4.6.3 Activate Filter group

Repeat the step for the text table, if needed. In the RDH Cockpit in Expert Mode select "Activate FilterGroups".

The screenshot shows the RDH Cockpit Settings dialog. There are several buttons arranged in a grid: 'Field Reduction', 'Enhancements', 'Overwrite Protection', 'Key-/Value-Mapping', 'FilterGroup(s)', and 'Activate FilterGroup(s)'. The 'Activate FilterGroup(s)' button is highlighted with a red box.

Choose the Sales Office "Filtergroup" and click "FilterCriteria".

The screenshot shows the 'Change View "RDM/H: FilterGroups": Overview' dialog. On the left, the 'Dialog Structure' tree shows 'RDM/H: FilterGroups' and 'RDM/H: FilterCriteria' selected. On the right, a table titled 'RDM/H: FilterGroups' shows several entries. The 'SALESOFFICE' entry is highlighted with a red box.

Activate the filters.

The screenshot shows the 'RDM/H: FilterCriteria' dialog. The table has columns: FilterGroup, Table Name, Field Name, Line, Active, INCL/EXCL, Option, and Selection. The first row, 'SALESOFFICE TVBUR', has the 'Active' checkbox checked. This checkbox is highlighted with a red box.

Select the entry and click "FilterSystems". Add the Filter group, table, receiver system and activate.




Dialog Structure		RDM/H: FilterSystems						
		FilterGroup	Table Name	Line	Line	Logical system	Logical Port	Aktiv
		SALESOFFICE	TVBUR	1	1	IH1400		<input checked="" type="checkbox"/>

Repeat the step for all Filter Criteria.

Go back to the RDH Cockpit in Send Mode and select Send.

- Choose your Configuration Group or enter the tables.
- Choose the logical system.
- Select SnapShot Mode.
- Select Detaillist and FilterGroup for options.



**ObjectSelection**

Table(s)  to

View(s)  to

Objectgroup(s) **SALESOFFICE**

FilterGroup(s) **SALESOFFICE**

**ALE / WebService**

MessageType **/ITG/GENERIC**

Logical System **IH1400**

Port for WebService

**Mode**

Transfer  Single  Bundle  SnapShot  Transport


**Options**

Scope	<input checked="" type="radio"/> with address	<input type="radio"/> without address
Heterogen	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Logging	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Changes	<input type="radio"/> Yes	<input checked="" type="radio"/> No
OnlineSele	<input type="radio"/> Yes	<input checked="" type="radio"/> No
Test	<input type="radio"/> Yes	<input checked="" type="radio"/> No
DetailList	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Filtergro.	<input checked="" type="radio"/> Yes	<input type="radio"/> No
Override	<input type="radio"/> Yes	<input checked="" type="radio"/> No

Click execute. Only the filtered entries should be shown.

Table Name	Short Description	Number
<b>Table Name</b>		
TVBUR	Organizational Unit: Sales Offices	2
TVBUR	100U1	100 U1 0000000524
TVBUR	100U2	100 U2 0000000543 SATTLERU
TVKBT	Organizational Unit: Sales Offices: Texts	2
TVKBT	100EU1	100 E U1 U1 Sales Office
TVKBT	100EU2	100 E U2 Sales Office Munich

Switch to the receiver system and check the entries for the SnapShot.



→IH110020251022105548	TVBUR	2	2	Organizational Unit: Sales Offices	TVBUR105548	TVBUR-AH-105548	SATTLERU	RDH
	TVKBT	11	2	Organizational Unit: Sales Offices: Texts	TVKBT105548		SATTLERU	RDH
	TVKGR	22	2	Organizational Unit: Sales Groups	TVKGR105548		SATTLERU	RDH
→IH140020251010091205								
	1003	52	52	Document Types	T003091205		SCORYG	RDH


ObjKey	From	To	Key	Name	Name 2	Name 3	Name 4	Conv. name	c/o	City	District	City Code	District	City	City Code	Sta
U1	01.01.0001	31.12.9999	0003	Itego												
Ü2	01.01.0001	31.12.9999	0003	U2 Company												

### 3.4.7 Expert Mode – Key Mapping

Key mapping is used to define and link different identifiers (keys) for the same business object. This allows the system to translate between various ID types used across separate systems, ensuring data consistency.

#### 3.4.7.1 Customize Key Mapping

In Expert Mode click "Key/Value-mapping".




Settings

Field Reduction      Enhancements

Overwrite Protection      Key-/Value-Mapping

FilterGroup(s)      Activate FilterGroup(s)

Select "Customizing".




KeyMapping

Customizing      Search

Maintain      Show


Select "Define Business Objects".



Create new entry and enter the Business Object and Constant Name. Save and go back.

BO Type	Description	Constant Name	Projection	Main OT
/ITR/TZONE	RDH: KeyMapping / Customers: Regional zones	TZONE	<input type="checkbox"/>	

Select "Define Object Identifier".



Create new entry and enter a description, the BO Type and the Constant Name.

Object ID Type	Description of Object ID Type	BO Type	Description of Business Object Type	Ob ID Constant Name	Int. Key	Lead. Key
/ITR/TZONE	RDH: KeyMapping / Debitoren: Regional... /ITR/TZONE	RDH: KeyMapping / Customers: Regional zones	TZONE	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Go back to the node "Define Business Objects" and add the Object ID Type Key.

BO Type	Constant Name	Projection	Main OT	Ob. ID Type Key St. Acc.	Object ID Type Desc.
/ITR/TZONE	TZONE	<input type="checkbox"/>		/ITR/TZONE	RDH: KeyMapping / Debitoren: Regionalzone


Go to Tx SE11 and enter a new Data Type → Create → Structure

<input checked="" type="radio"/> Data type	/ITR/KEY_MAP_LAND1
<input type="radio"/> Type Group	
Structure	
/ITR/KEY_MAP_LAND1 Active	
Short Description	RDH: KeyMapping / TZONE-Key
Attributes	Components Input Help/Check Currency/quantity fields
Built-In Type	
Component	Typing Method Component Type Data Type Length Decim. Coordinate Short Description
LAND1	Types LAND1 CHAR 3 0 0 Country/Region Key
ZONE1	Types LZONE CHAR 10 0 0 Transportation zone to or from which the goods are delivered

Save under Package /ITR/RDH\_KM and activate it.




Go back and select "Assign Key Structures to Object Identifiers".



Create a new entry and enter the values for the Object ID Type with the created Key Structure.

Assign Key Structures to Object Identifiers					
Object ID Type	Description of Object ID Type	Key Structure	Delimiter	BO Type	Description of BO Type
/ITR/TZONE	RDH: KeyMapping / Debitoren: Regional zones	/ITR/KEY_MAP_LAND1		/ITR/TZONE	RDH: KeyMapping / Debitoren: Regional zones

Go back and select "Assign Business Objects to Main Context".



Create new entry. Enter the Main Context "SAPdefaultMapping."


Assign Business Objects to Main Contexts			
BO Type	Description	Main Context	Search
/ITR/TZONE	RDH: KeyMapping / Customers: Regional zones	SAPdefaultMapping	

### 3.4.7.2 Maintain Key Mapping.


Go back to the Key-Mapping Overview in RDH and select "Maintain".



Choose your Business Object Type



Click Edit and enter the Country and the Transport zone.




Add the mapping.

Mapped Objects

<input type="checkbox"/>	* No.	* System ID	* Business Obj...	Object ID Type	* Object ID
<input type="checkbox"/>	1	IH1100	RDH: KeyMappin...	RDH: KeyMappin...	68 DE 0000000002
<input type="checkbox"/>	2	IH1400	RDH: KeyMappin...	RDH: KeyMappin...	68 DE 1000000002

### 3.4.7.3 Show Key Mapping

Go back to the Key-Mapping Overview in RDH and select "Show".



It should show the created Mapping.

SAP RDH: Show Key-Mapping

Table	Sender	from-Value	Receiver	to-Value
Table	IH1100	DE 0000000002	IH1400	DE 1000000002

### 3.4.7.4 Search Key Mapping

Go back to the Key-Mapping Overview in the RDH and select "Search".



Select the Business Object type /ITR/TZONE and start the search.



SAP Search Key Mapping

Start Search

Selection Criteria

Bus. Obj. Type: RDH: KeyMapping / Customers: Re...

Object ID Type:

Business System:

ID Value:

The Mapping should be shown.



Object ID	ID Value	Object ID Type	Description of Object ID Type	Bus. Sys.	Mapping Group ID
6045BD8B74AC1FD0AC858487BA39432	DE 0000000002	ITR/TZONE	RDH: KeyMapping / Debitoren: Regionalzonen	IH1100	6045BD8B74AC1FD0AC858487BA39C328
6045BD8B74AC1FD0AC858487BA39832	DE 1000000002	ITR/TZONE	RDH: KeyMapping / Debitoren: Regionalzonen	IH1400	6045BD8B74AC1FD0AC858487BA39C328

### 3.4.8 Expert Mode – Value Mapping

Value Mapping ensures that data values used in your MDG system are consistently mapped to the corresponding external code values used by connected receiving or sending business systems

#### 3.4.8.1 Create Value Mapping

In Expert Mode click "Key/Value-mapping".



Settings

Field Reduction

Enhancements

Overwrite Protection

Key-/Value-Mapping

FilterGroup(s)

Activate FilterGroup(s)

Select "Customizing".



KeyMapping

Customizing

Search

Maintain


Show

ValueMapping

Customizing

Show


Select "Maintain Value Mapping".




Create a new Entry. Choose "Data Element" as Object Type, enter the Global Data Type and the Input Help. Client Dep. must be checked.




Save and confirm with enter, also when errors come up and go to Tx SE16 and search for the table.




Choose an entry. In this case Region East.



Go back to the "Maintain Value Mapping" Screen and click on "Navigation".



Create a new entry.



Enter the List agency ID, List ID and the Version.

Mapping ID	List Agency ID	List ID	List Version ID	Int
01	/ITR/TZONE/ZONE1	/ITR/TZONE/ZONE1	01	

Select the created entry and click on "Define Value Mapping". Maintain the External Code Value.

The screenshot shows the SAP Fiori interface for defining value mapping. The 'Object Type' is set to 'DTEL' and the 'Global Data Type' is '/ITR/TZONE/ZONE1'. The 'Mapping ID' is '01'. In the 'Define Value Mapping' table, there is one entry with 'Map Comb.' '1', 'Internal Code Value' '0000000001', 'Description' (empty), and 'External Code' '1000000001' highlighted with a yellow box.

Go back and Choose "Assign Code Lists ..."

The screenshot shows the SAP Fiori interface for value mapping. Under the 'Value Mapping' structure, the 'Assign Code Lists to Elements and Systems' option is highlighted with a yellow box.

Create new entry. Enter the values below

SAP Change View "Assign Code Lists to Elements and Systems": Overview				
Assign Code Lists to Elements and Systems		List ID	List Agency ID	List Version ID
Type	Global	Internal List ID	Business System	
Data... /ITR/T_ 01		IH1400	/ITR/TZONE/ZONE1	01


Go back and select "Define Technical Settings for Business System".

The screenshot shows the SAP Fiori interface for value mapping. Under the 'Value Mapping' structure, the 'Define Technical Settings for Business Systems' option is highlighted with a yellow box.

Enter the Business System.

Define Business Systems		
Business System	Logical System	RFC Destination
ER9CLNT003	ER9CLNT003	
ER9CLNT500	ER9CLNT500	
IH1100	IH1100	
IH1400	IH1400	IH1400
IH1CLNT100	IH1CLNT100	IH1CLNT100

Go back to the Key-Value Mapping Overview and select Show,



KeyMapping

Customizing      Search

Maintain      Show



ValueMapping


Customizing      Show



Import/Export

KM-/VM-Import      KM-/VM-Export

You should now see your created entry.



SAP RDH: Show Value-Mapping


RDH: Show Value-Mapping

Type Global Data Type BS List ID List Agency ID List ID List Ver. Map Comb. Int. Code Val Ext. Code Val

DTEL /ITR/TZONE/ZONE1 IH1400 01 /ITR/TZONE/ZONE1 /ITR/TZONE/ZONE1 01 1 0000000001 10000000001

### 3.4.9 Expert Mode – Enhancements

Enhancements can be used to implement additional logic like customized data adjustments, defaulting, or value mappings. Select Enhancements in Expert Mode or use transaction /ITR/CUSTCODE.



Settings

Field Reduction      Enhancements      Overwrite Protection

SAP Display View "RDM: special customer handling": Overview




Table Name	Function Module	A
Idoc-Inbound	/ITR/RDH_LOGGING_RECEIVER_SIDE	<input checked="" type="checkbox"/>
Idoc-Inbound (...	/ITR/RDM_FOREIGN_KEY_CHECK	<input checked="" type="checkbox"/>
/ITR/ADDR	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/MDIP	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/MDLG	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/MDLL	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/MDLV	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/MDLW	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T001	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T001L	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T001W	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T002	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T002T	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T003	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T003T	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T004	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T004T	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T005	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T005S	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>
/ITR/T005T	/ITR/RDM_LSA_TO_CUST	<input checked="" type="checkbox"/>

Various events can be chosen (e.g. Event 6: RDH-Snapshot/Enhancement)





Table Name	
/ITR/ADDR	Idoc/WS-Outbound
Idoc-Inbound	
Adapter PROCESSING	
Adapter FINALIZE	
Idoc/WS-Outbound	
Idoc-Inbound (Check/Change after Unpack)	
RDH-SnapShot/Enhancement	

And various implementations can be assigned. Please check function modules which can be found by searching SE37 for "/ITR/\*TEMPLATE\*EVENT\*". For example:



Function group	Function group short text
Function Module Name	Short text for function module
/ITR/RDM_FOREIGN	
/ITR/RDH_TEMPLATE_EVENT_ID_5	
/ITR/RDH_TEMPLATE_EVENT_ID_6	

## 4 Reference Data Object Types (Content)

### 4.1 Content for Reference Data Harmonization (RDH)

Based on the generic Master Data Framework (MDF), RDH can harmonize and synchronize **all** SAP tables.

Using "Configuration Groups" tables which should be harmonized can be grouped into one or many groups. Based on groups filters can be used to restrict the reference data values which should be in scope.

"Business Objects" help to define dependencies between configuration tables and with this create complete objects which can be harmonized as a complete object rather than a set of tables.

Predefined Configuration Groups for common scenarios like a MDG implementation (for Materials, Business Partners or Financials) or a Financial Reporting Structure replication can be provided by Itego. Please contact [support@itego.de](mailto:support@itego.de) (subject: "Predefined Configuration Groups").

### 4.2 Content for Reference Data Governance (RDG)

RDM delivers the central governance for reference data aligned to the functionalities offered in the SAP Reference Implementation Guide (IMG) available through transaction SPRO. For each object change request types, message types and other components are delivered which are described below.

Financials, HR, General Settings				
Business Area	Chart of Accounts	Company Code	Company ID	Controlling Area
Customer Acc. Group	Currency	Document Type	Exchange Rate	Functional Area
Gen.Ledger Acc. Group	Operating Concern	Posting Period Variant	Tax Code	Valuation Class
Vendor Acc. Group	Personnel Area	Country & Region	Holiday Cal & Pub. Hol.	Language

Logistics and Purchasing				Sales & Distribution	
BOM Usage	Division	Factory Calendar	Laboratory/Office	Distribution Channel	Incoterms
Location	Material Group	Material Status	Material Type	Payment Terms	Product Hierarchy
MRP Area	MRP Controller	MRP Profile	MRP Type	Sales Group	Sales Organization
Plant	Storage Location	Unit of Measure	Characteristics	Sales Office	Shipping Conditions
Classes	Planning Scope	Purchasing Group	Purchasing Org.	Shipping Type	Shipping Point

---

Details for each of these object types are provided in the following sections.

For all objects Meta Data can be maintained. This can be done by adding files or links that can be used to describe the reference data object in more detail. Examples: Usage scenario of a specific Material Group. Formulas used for a Unit of Measure.

Reference data objects which are part of RDM and do have dependencies are usually linked to each other as part of the data model. Example: Country and Region. This allows to use "active" data in MDG which is not necessarily already in productive usage. If needed this can be changed on a project basis. Example: Country within Region could reference customizing table T005 which would restrict the selection to countries which are in productive usage.

Dependencies to reference data objects which are not in the scope of RDM are implemented as a reference to the specific customizing table which needs to be synchronized within the system landscape.

## 4.2.1 Financials

### 4.2.1.1 Account Group for General Ledger Accounts

Account Groups for General Ledger Accounts are based on a Chart of Accounts and are used to define number ranges as well as optional and mandatory fields for accounts in this account group. The following attributes (based on view V\_T077S with tables T077S and T077Z) can be maintained:

Attribute	Properties, Comments, Configuration Table
CoA	Chart of Accounts
Account Group	G/L Account Group
Name	Language dependent text
From G/L account	Number of G/L account (lower area limit)
To G/L account	Number of G/L Account (Upper Area Limit)

Change Request Types available:

CR Type	Description	Properties, Comments
IAF1S01	Create G/L Acc.Gr. and activate	Create, 1-step
IAF1S02	Process G/L Acc.Gr. and activate	Change, 1-step
IAF1SL1	Load G/L Acc.Gr. and activate	Load, 1-step
IAF2S01	Create G/L Acc.Gr. with approval	Create, 2-step
IAF2S02	Process G/L Acc.Gr. with approval	Change, 2-step
IAF2SL1	Load G/L Acc.Gr. with approval	Load, 2-step
IAF3S01	Create G/L Acc.Gr. with proc. and appr.	Create, 3-step
IAF3S02	Process G/L Acc.Gr. with proc. and appr	Change, 2-step

### 4.2.1.2 Account Group for Vendors

Account Groups for Vendors and are used to define number ranges as well as optional and mandatory fields for vendors in this account group. The following attributes (based on view V\_T077K with tables T077K and T077Y) can be maintained:

Attribute	Description
Account group	Vendor account group
Name	Language dependent text
One-time account	Indicator: Account group for one-time accounts?

Change Request Types available:

CR Type	Description	Properties, Comments
IAV1S01	Create Vend.Acc.Gr. and activate	Create, 1-step
IAV1S02	Process Vend.Acc.Gr. and activate	Change, 1-step
IAV1SL1	Load Vend.Acc.Gr. and activate	Load, 1-step
IAV2S01	Create Vend.Acc.Gr. with approval	Create, 2-step
IAV2S02	Process Vend.Acc.Gr. with approval	Change, 2-step
IAV2SL1	Load Vend.Acc.Gr. with approval	Load, 2-step
IAV3S01	Create Vend.Acc.Gr. with proc. and appr	Create, 3-step
IAV3S02	Process Vend.Acc.Gr. with proc and appr	Change, 2-step

#### 4.2.1.3 Account Group for Customers

Account Groups for Customers and are used to define number ranges as well as optional and mandatory fields for customers in this account group. The following attributes (based on view V\_T077D with tables T077D, T077X and TKUPA) can be maintained:

Attribute	Description
Account group	Customer Account Group
Name	Language dependent text
One-time account	Indicator: Account group for one-time accounts?
Procedure	Output determination procedure

Change Request Types available:

CR Type	Description	Properties, Comments
IAC1S01	Create Cust.Acc.Gr. and activate	Create, 1-step
IAC1S02	Process Cust.Acc.Gr. and activate	Change, 1-step
IAC1SL1	Load Cust.Acc.Gr. and activate	Load, 1-step
IAC2S01	Create Cust.Acc.Gr. with approval	Create, 2-step
IAC2S02	Process Cust.Acc.Gr. with approval	Change, 2-step
IAC2SL1	Load Cust.Acc.Gr. with approval	Load, 2-step
IAC3S01	Create CustAccGr with proc. and appr.	Create, 3-step
IAC3S02	Process CustAccGr with proc. and appr.	Change, 2-step

#### 4.2.1.4 *Business Area*

A Business Area is used for reporting both internal and external. It is defined as an organizational area. The following attributes can be maintained:

Attribute	Description
Business Area	Business Area
Description (medium text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IGS1S01	Create Business Area and activate	Create, 1-step
IGS1S02	Process Business Area and activate	Change, 1-step
IGS1SL1	Load Business Area and activate	Load, 1-step
IGS2S01	Create Business Area with approval	Create, 2-step
IGS2S02	Process Business Area with approval	Change, 2-step
IGS2SL1	Load Business Area with approval	Load, 2-step
IGS3S01	Create Business Area with proc. and appr	Create, 3-step
IGS3S02	Process Business Area with proc and appr	Change, 3-step

#### 4.2.1.5 *Chart of Accounts*

The Chart of Accounts is used to maintain the G/L Accounts which themselves are used by Company Codes. The following attributes can be maintained:

Attribute	Description
Chart of Accounts	Chart of Accounts
Alternative language	Alternative languages
Maint.language	Maintaining language
Controlling integration	Type of integration between G/L accounts and cost elements
Group Chart of Accts	Group Chart of Accts
Central layout	Central layout
Chart of accts layout	Chart of accts layout
Company code layout	Company code layout
Trading partner cannot be entered	Trading partner cannot be entered
Length of G/L account number	Significant length of the G/L account number

Description (long text)	Language dependent text
Blocked	Indicator: is the chart of accounts blocked ?

Change Request Types available:

CR Type	Description	Properties, Comments
IKP1S01	Create Chart of Accounts and activate	Create, 1-step
IKP1S02	Process Chart of Accounts and activate	Change, 1-step
IKP1SL1	Load Chart of Accounts and activate	Load, 1-step
IKP2S01	Create Chart of Accounts with approval	Create, 2-step
IKP2S02	Process Chart of Accounts with approval	Change, 2-step
IKP2SL1	Load Chart of Accounts with approval	Load, 2-step
IKP3S01	Create Chart of Accounts with proc. and appr	Create, 3-step
IKP3S02	Process Chart of Accounts with proc and appr	Change, 3-step

#### 4.2.1.6 Company Code

Company Codes are used to structure the business organization from a financial accounting perspective. The following attributes can be maintained:

Attribute	Description
Company Code	Company Code ID
Company Name	Name of Company Code or Company
Long Name	(Long) Name of Company Code
City	City
Country	Country
Currency	Currency Code
Language Key	Language
Address	Address details

Additional Attributes available in the Data Model:

Attribute Description
Additional settings variant for bus.area financial statements
Name of global company code
Company Code Variant (Screen)
Foreign Trade: Screen ctrl of imp.data f. MM-goods receipt
Document Type for Journal Voucher (Amount Correction)

Deferred Tax Rule
Document Type for Provisions for Taxes on Services Received
Document Type for Journal Voucher (Tax Code Correction)
Document Type for Remittance Challans
Original Key of the Company Code
Cash Management and Forecast Company Code
Financial Management Area
Funds center can be assigned to an account in HR from
Activate Account Assignment Derivation in Funds Management
Field Status Variant
Funds reservation field status var.
Foreign Trade: Import Data Control in MM Purchase Orders
Inflation Method
Credit control area Credit control area
Allocation Indicator
Foreign trade: Import data copying control for GR
Chart of Accounts According to Country Legislation
Rules for Copying from the Sample Account for G/L Accounts
Output Tax Code for Non-Taxable Transactions
Input Tax Code for Non-Taxable Transactions
Method for offsetting account determination
Posting Period Variant
Fiscal Year Variant
Procedure for Setting the Posting Date
Manage Variant of Posting Period for Company Code/Ledger
Company
VAT Registration Number
Surcharge Calculation Method
Jurisdiction for tax calculation - tax jurisdiction code
Foreign Currency Translation for Tax Items
Sales/Purchases Tax Group
Maximum exchange rate deviation in percent
Workflow variant
Indicator: Extended withholding tax active
G/L account authorization check in purchase requisitions
G/L account authorization check in PO/scheduling agreement
G/L account authorization check in inventory management
G/L account authorization check in contracts
G/L account authorization check in shopping cart
Enable Amount Split
Accounts Receivable Pledging Active

Cost of sales accounting status
Indicator: hedge request active
Indicator: Purchase Account Processing is Active
Indicator: Company code is in another system
Indicator: Cash Management activated?
Indicator: Updating MM in Cash Mgmt/Forecast activated?
Indicator: Updating SD in Cash Mgmt/Forecast activated?
Activate Update in Funds Management
Indicator: Cash budget management active
Indicator: Project Cash Management active?
Indicator: Propose fiscal year ?
Indicator: Business area financial statements required?
Indicator: JVA Active
Indicator: Post translations for exchange rate differences?
Indicator: Can credit control area be overwritten?
Indicator: Base amount for tax is net of discount?
Indicator: Negative Postings Permitted
Indicator: Productive company code?
Indicator: Discount base amount is the net value
Indicator: No ex.rate difference when clearing in local crcy
Indicator: Document date as the basis for tax determination
Indicator: Propose current date as value date?
Tax Reporting Date Active in Documents
Indicator: Financial Assets Management active

Change Request Types available:

CR Type	Description	Properties, Comments
ICC1S01	Create Company Code and activate	Create, 1-step
ICC1S02	Process Company Code and activate	Change, 1-step
ICC1SL1	Load Company Code and activate	Load, 1-step
ICC2S01	Create Company Code with approval	Create, 2-step
ICC2S02	Process Company Code with approval	Change, 2-step
ICC2SL1	Load Company Code with approval	Load, 2-step
ICC3S01	Create Company Code with proc. and appr	Create, 3-step
ICC3S02	Process Company Code with proc and appr	Change, 3-step

#### 4.2.1.7 Company ID

A unique identifier for a company or legal entity within a system or data environment. It is used to clearly distinguish one organization from another for financial, administrative, or master-data purposes.

Attribute	Description
NAME1	Company name
NAME2	Name of company 2
CITY	City where company is located
POBOX	Post office box of the company
RCOMP	Company
PSTLC	Global company zip code
STRET	Street address of the company
LANGU	Language Key
CURR	Local Currency
MCOMP	Master data company code
CNTRY	Country of Company

Change Request Types available:

CR Type	Description	Properties, Comments
ICM1S01	Create Company Id and activate	Create, 1-step
ICM1S02	Process Company Id and activate	Change, 1-step
ICM1SL1	Load Company Id and activate	Load, 1-step
ICM2S01	Create Company Id with approval	Create, 2-step
ICM2S02	Process Company Id with approval	Change, 2-step
ICM2SL1	Load Company Id with approval	Load, 2-step
ICM3S01	Create Company Id with proc. and appr.	Create, 3-step
ICM3S02	Process Company Id with proc. and appr	Change, 3-step

#### 4.2.1.8 Controlling Area

A Controlling Area includes several Company Codes. It is used for cost accounting purposes. The following attributes can be maintained:

Attribute	Description
Controlling Area	Controlling Area
Distribution Method	Distribution Method
Name	Name of the controlling area
Document type	Document type
Hierarchy Area	Hierarchy Area

Hierarchy 1	Use First Alternative Hierarchy for Authorizations
Hierarchy 2	Use Second Alternative Hierarchy for Authorizations
Do Not Use Std Hier.	Do Not Use Standard Hierarchy for Authorizations
Currency Type	Currency Type for Controlling Area
C&V Profile Active	Ind.: Currency and Valuation Profile Active
Currency and Valuation Profile	Currency and Valuation Profile
Operating concern	Operating concern
FM Area	Financial Management Area
Hierarchy 1	Use First Alternative Hierarchy for Authorizations
Hierarchy 2	Use Second Alternative Hierarchy for Authorizations
Do Not Use Std Hier.	Do Not Use Standard Hierarchy for Authorizations
Std. Hierarchy	Do Not Use Standard Hierarchy for Authorizations
Description	Language dependent text
CoCd -> CO Area	Allocation Indicator
Productive indicator	Productive indicator for controlling area
Convert revenue	Indicator: Revenue must be converted
Reserve	Indicator: reserve (not used at present)
Chart of Accounts	Chart of Accounts
Currency	Currency Key
Fiscal Year Variant	Fiscal Year Variant
Logical System	Logical System
LSystem master data	Logical system for master data maintenance
Profit Center Local Currency	Local Currency for Profit Center Accounting
Currency type for Profit Ctr Acctg	Currency type of the profit center report currency
Transaction currency	Store transaction currency in EC-PCA
Account control transfer valuation diff.	Account control when transferring valuation differences
ALE distribution method	Method for Distributing Profit Centers Using ALE
Valuation View	Valuation View
Elim.Intern.Bus.Vol	Elimination of internal bus. volume for Profit Center Acctg
Profit ctr ledger	Profit center ledger
Hierarchy Area	Profit center area
Recon.Ledger	Reconciliation Ledger Active
Acct determination for primary CEIms	Reconciliation Ledger: Acct Determination for Primary CEIms
ValView for CalcBase	Valuation View for Calculation Base
Description (medium text)	Description (medium text)
Person Responsible	Person Responsible for the Controlling Area

Bus.Proc. ALE active	Indicator: ALE for active business process (process costs)
Diff. CCode Currency	Indicator: Different Company Code Currency is Allowed
Fiscal Year	Fiscal Year
AA: Activity Type	Account Assignment: Activity Type Active
Group Name	Group Name
Group Name	Group Name
All Currencies	Update all Currencies
Asset Accounting	Asset Accounting Active
Order Management	Order Management Active
Acty-Based Costing	Activity-Based Costing Active
ProfitAnalysis	Profitability analysis active
Fiscal Year	Fiscal year
Gener./ledger active	General ledger system active
Funds Management	Funds management active
Inc. sales orders	Inc. sales orders
Group Name	Group Name
Group Name	Group Name
Costing	CO product costing active
Cost Centers	Cost Center Accounting Active
Cost Objects	Cost Objects Active
Commit. Management	Order commitment management active
W. Commit. Mgt	W. Commit. Mgt
Profit Center Acctg	Profit Center Accounting is active
Profit center valuation	Profit center valuation
Projects	Projects active
Variances	Compute with variances
Real Estate Mgmt	Field is used
Down payments	Update of down payments to projects and orders
C Man. & Forecast	FI financial budgeting is active
Customer master	FI cust.master active
Payments	Update payments assigned to projects
CoCd Validation	CO Company Code Validation
Purchasing	Purchasing is active
Product costing	Product costing is active
Human Resources	Human Resources is active
Sales Orders	SD Order Processing is Active
Billing document	SD Billing is active
Company Name	Name of Company Code or Company

Change Request Types available:

CR Type	Description	Properties, Comments
IKO1S01	Create Controlling Area and activate	Create, 1-step
IKO1S02	Process Controlling Area and activate	Change, 1-step
IKO1SL1	Load Controlling Area and activate	Load, 1-step
IKO2S01	Create Controlling Area with approval	Create, 2-step
IKO2S02	Process Controlling Area with approval	Change, 2-step
IKO2SL1	Load Controlling Area with approval	Load, 2-step
IKO3S01	Create Controlling Area with proc. and appr	Create, 3-step
IKO3S02	Process Controlling Area with proc and appr	Change, 3-step

#### 4.2.1.9 *Currency Code*

Currency Codes are defined for all currencies which occur in business transactions and usually are aligned with the ISO Codes. The following attributes can be maintained:

Attribute	Description
Currency Code	Currency
Description long	Description (Long Text)
Description short	Description (Short Text)
ISO Code	ISO currency code
Primary SAP Code	Primary SAP Currency Code for ISO Code
Alternative Key	Alternative key for currencies
Valid until	Date until which the currency is valid

Change Request Types available:

CR Type	Description	Properties, Comments
ICU1S01	Create Currency and activate	Create, 1-step
ICU1S02	Process Currency and activate	Change, 1-step
ICU1SL1	Load Currency and activate	Load, 1-step
ICU2S01	Create Currency with approval	Create, 2-step
ICU2S02	Process Currency with approval	Change, 2-step
ICU2SL1	Load Currency with approval	Load, 2-step
ICU3S01	Create Currency with proc. and appr	Create, 3-step
ICU3S02	Process Currency with proc and appr	Change, 2-step

#### 4.2.1.10 Document Type

Document Types are used to classify Documents. The main fields of application are accounting, and business transactions. The following attributes can be maintained:

Attribute	Description
Document type	Document type
Document Class	Document Class
Authorization Group	Authorization Group
Account types	Account types
Ex.rate type for forgn crncy docs	Ex.rate type for forgn crncy docs
Number range	Number range
Rec.Indicator Credit	Rec.Indicator Credit
Debit Rec.Indicator	Rules for Issuing an Invoice
Reverse DocumentType	Reverse Document Type
Description (short text)	Language dependent text
Act.allocation	Act.allocation
Plan.allocation	Plan.allocation
Check Date	Check Date
Inter-company postgs	Inter-company posting
Only one customer/vendor allowed?	Indicator: Only one customer/vendor allowed
Assets	Indicator: Are postings to assets permitted?
Customer	Indicator: Are postings to customer permitted?
Vendor	Indicator: Are postings to vendor permitted?
Material	Indicator: Are postings to material account permitted?
G/L account	Indicator: Are postings to G/L account permitted?
Market Data Exchange Rate	Market data Exchange Rate
Enter trading part.	Indicator: Trading partner can be entered manually
Reference number	Indicator: Reference number
Long Invoice reference required	Long Invoice Reference Required
Document header text	Indicator: Document header text
Negative Postings Permitted	Negative postings permitted
Net document type	Indicator: Document posted net?
Doc.type for subseq.ad-justmnt	Indicator: Document type for posting subsequent adjustment

Planning	Planning
Post to Position Accounts	Futures Account Text Field
Rollup	Rollup
SAP billing document	Indicator: Posting from SAP billing document?
Batch input only	Indicator: Document type can only be used in batch input
Assignment to Acctg Principles Is Unique	Accounting Principle Assignment Is Unique in Document
Init.acct assignment	Indicator: Document type for initial account assignment?
Ex.rate dif.part pyt	Ex.rate dif.part pyt

Change Request Types available:

CR Type	Description	Properties, Comments
IBT1S01	Create Document Type and activate	Create, 1-step
IBT1S02	Process Document Type and activate	Change, 1-step
IBT1SL1	Load Document Type and activate	Load, 1-step
IBT2S01	Create Document Type with approval	Create, 2-step
IBT2S02	Process Document Type with approval	Change, 2-step
IBT2SL1	Load Document Type with approval	Load, 2-step
IBT3S01	Create Document Type with proc. and appr	Create, 3-step
IBT3S02	Process Document Type with proc and appr	Change, 3-step

#### 4.2.1.11 Exchange Rate

Exchange Rates allow the operator to calculate the difference between two currencies. Exchange Rates in RDM represent a special case as the data is updated from external sources (e.g. the ECB) on a daily basis. Incoming Exchange Rates that do not alternate the current value beyond a certain limit are approved automatically. Exchange Rates that deviate beyond this mentioned border have to be approved by a specialist first. The following attributes can be maintained:

Attribute	Description
Exchange Rate (Type)	Exchange Rate (Type)
Currency (from)	Currency value from
Currency (to)	Currency value to
Valid from	Valid from
Alt. exch.rate type	Alternative Exchange Rate type

Alt.e/r type valid fr.	Alternative e/r type valid from
Exchange Rate	Exchange Rate
Quotation type	Quotation type
Ratio (from)	Ration (from)
Ratio (to)	Ration (to)

Change Request Types available:

CR Type	Description	Properties, Comments
ICR1S01	Create Exchange Rate and activate	Create, 1-step
ICR1S02	Process Exchange Rate and activate	Change, 1-step
ICR1SL1	Load Exchange Rate and activate	Load, 1-step
ICR2S01	Create Exchange Rate with approval	Create, 2-step
ICR2S02	Process Exchange Rate with approval	Change, 2-step
ICR2SL1	Load Exchange Rate with approval	Load, 2-step
ICR3S01	Create Exchange Rate with proc. and appr	Create, 3-step
ICR3S02	Process Exchange Rate with proc and appr	Change, 3-step
ICR3SL1	Load Curr ExRT, process and activate	Automatic import from external source

Please also have a look at the object specific documentation for "Exchange Rates".

#### 4.2.1.12 Functional Area

A Functional Area is an organizational area. It classifies the expenses of a company in the following fields: Functions Administration, Sales and Distribution, Marketing, Production, Research and Development. The following attributes can be maintained:

Attribute	Description
Functional Area	Functional Area
Authorization Group	Authorization Group
Valid from	Valid-From Date
Valid to	Valid to date
Expiration Date	Expiration Date
Functional Area Substring 1	Functional Area Substring 1
Functional Area Substring 2	Functional Area Substring 2
Functional Area Substring 3	Functional Area Substring 3

---

Master Data Subdivision ID	Master Data Subdivision ID
Description (medium text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IFK1S01	Create Functional Area and activate	Create, 1-step
IFK1S02	Process Functional Area and activate	Change, 1-step
IFK1SL1	Load Functional Area and activate	Load, 1-step
IFK2S01	Create Functional Area with approval	Create, 2-step
IFK2S02	Process Functional Area with approval	Change, 2-step
IFK2SL1	Load Functional Area with approval	Load, 2-step
IFK3S01	Create Functional Area with proc. and appr	Create, 3-step
IFK3S02	Process Functional Area with proc and appr	Change, 3-step

#### 4.2.1.13 Operating Concern

An Operating Concern is an organizational unit. It defines the extent of the marketing and sales information that can be reported in combination. Every Operating Concern is being assigned by at least one Controlling Area. The following attributes can be maintained:

Attribute	Description
Operating Concern	Operating Concern
Distribution	Distribution
Period block	Period block
Industry version	Industry version
Created On	Created On
Created in Release	Created in Release
Operating Concern Status	Operating Concern Status
Operating Concern Status	Operating Concern Status
Environment	Environment
Operating Concern Status	Operating Concern Status
Currency	Currency
FLGCUR1	FLGCUR1
FLGCUR2	FLGCUR2
FLGCUR3	FLGCUR3
Obj. name	Object name
Message Type	Message Type

Client	Client
Type of Profit. Analysis	Type of Profit. Analysis
Fiscal Year Variant	Fiscal Year Variant
Program Version	Version number
SAP Release	SAP Release
Original op.concern	Original Operating Concern
System type	Communication application
Description (medium text)	Language dependent text
Act. 2nd per. type	Indicator: Update actual data in the second period type
Plan 2nd per. type	Indicator: Update plan data in the 2nd period type
Field Name	Field Name
Flag: Type of use	Flag: Type of use

Change Request Types available:

CR Type	Description	Properties, Comments
IER1S01	Create Operating Concern and activate	Create, 1-step
IER1S02	Process Operating Concern and activate	Change, 1-step
IER1SL1	Load Operating Concern and activate	Load, 1-step
IER2S01	Create Operating Concern with approval	Create, 2-step
IER2S02	Process Operating Concern with approval	Change, 2-step
IER2SL1	Load Operating Concern with approval	Load, 2-step
IER3S01	Create Operating Concern with proc. and appr	Create, 3-step
IER3S02	Process Operating Concern with proc and appr	Change, 3-step

#### 4.2.1.14 Posting Period Variant

A valuation class is used for the automatic determination of G/L accounts in material document posting.

Attribute	Description
OPVAR	Posting Period Variant
SPRAS	Language Key
OPVAR	Posting Period Variant
OPVTX	Posting Period Variant Name

Change Request Types available:

CR Type	Description	Properties, Comments
IOP1S01	Create Posting Period Variant & activate	Create, 1-step

IOP1S02	Process Posting Period Variant &activate	Change, 1-step
IOP1SL1	Load Posting Period Variant & activate	Load, 1-step
IOP2S01	Create Posting Period Var with approval	Create, 2-step
IOP2S02	Process Posting Period Var with approval	Change, 2-step
IOP2SL1	Load Posting Period Var with approval	Load, 2-step
IOP3S01	Create Post Per Var with proc. and appr.	Create, 3-step
IOP3S02	Process Post Per Var with proc. and appr	Change, 3-step

#### 4.2.1.15 Tax Code

Tax codes are sequenced collections of one or more tax components that define the tax rates applied on line items and define how to calculate the tax amount.

Attribute	Description
AUFTL	Target Tax Code (for Deferred Tax)
EGRKZ	'Tax Relevant' Indicator (Only for External Tax System)
J1BISS	Tax Calculation: Service Without ICMS/IPI
J1BTAXL1	Tax law: ICMS
J1BTAXL2	Tax law: IPI
J1BTAXL4	COFINS Tax Law
J1BTAXL5	PIS Tax Law
J1BTXICE	ICMS Stored as "Exempt" Instead of "Other Basis"
J1BTXIPE	IPI Stored as "Exempt" Instead of "Other Basis"
J1BUSAGE	Tax Calculation: Material Usage
LAND1_TAX	Country Key
LSTML	Tax law: IPI
MOSSC1	MOSS Tax Reporting Country for Electronic Service
MWART	Indicator: Tax code for sales taxes
NEWDEFTA	New Deferred Tax Code: Yes/No
OSS_CLASS	OSS Classification
PROCD	Tax Calculation: Material Usage
PRUEF	EU Code / Code
TOLERANC	Tolerance Percentage Rate for Tax Calculation
TXIND	Tax Calculation: Service Without ICMS/IPI
TXREL	Tax law: ICMS
XINACT1	Set Tax Code to "Inactive" - No Further Use
XMSTU	SAP internal product code (external interface)
XSLTA1	Country for Tax Return
ZMWSK	Tax Category for US Taxes

---

ZMWSKESA	Target Tax Code for Deferred EU Acquisition Tax, Output Tax
ZMWSKESE	Target Tax Code for Deferred EU Acquisition Tax, Input Tax

Change Request Types available:

<b>CR Type</b>	<b>Description</b>	<b>Properties, Comments</b>
ITX1S01	Create Tax Code and activate	Create, 1-step
ITX1S02	Process Tax Code and activate	Change, 1-step
ITX1SL1	Load Tax Code and activate	Load, 1-step
ITX2S01	Create Tax Code with appr.	Create, 2-step
ITX2S02	Process Tax Code with appr.	Change, 2-step
ITX2SL1	Load Tax Code with appr.	Load, 2-step
ITX3S01	Create Tax Code with proc. and appr	Create, 3-step
ITX3S02	Process Tax Code with proc. and app	Change, 3-step

#### 4.2.1.16 *Valuation Class*

A valuation class is used for the automatic determination of G/L accounts in material document posting.

Attribute	Description
KKREF	Account category reference

Change Request Types available:

CR Type	Description	Properties, Comments
IVC1S01	Create Valuation Class and activate	Create, 1-step
IVC1S02	Process Valuation Class and activate	Change, 1-step
IVC1SL1	Load Valuation Class and activate	Load, 1-step
IVC2S01	Create Valuation Class with appr.	Create, 2-step
IVC2S02	Process Tax Code with appr.	Change, 2-step
IVC2SL1	Load Valuation Class with appr.	Load, 2-step
IVC3S01	Create Valuation CL with proc. and appr	Create, 3-step
IVC3S02	Process Valuation CL with proc. and app	Change, 3-step

## 4.2.2 Human Resources

#### 4.2.2.1 *Personnel Area*

A Personnel Area is a subunit of a Company Code and is divided into several sub-areas. It is used for managing workforce, time and payroll. The following attributes can be maintained:

Attribute	Description
Personnel area	Personnel Area
City code	City Code
County code	County Code
Country Grouping	Country Grouping
Name 2	Name 2
City	City
Company Code	Company Code
Country Key	Country Key
Region	Region
PO Box	PO Box
Postal Code	Postal Code
Description	Language dependent text

---

Street and House No.	Street and House Number
Description (medium text)	Language dependent text
Address group	Address Group (Key) (Business Address Services)
City	City
c/o	Coname
House Number	House Number
Country Key	Country Key
Name	Language dependent text
Name 2	Language dependent text
Name 3	Language dependent text
Name 4	Language dependent text
Postal Code	City postal code
Region	Region
Description	Language dependent text
Search Term 1	Search Term 1
Search Term 2	Search Term 2
Street	Street
Title	Form-of-Address Key
Tax Jurisdiction	Tax Jurisdiction
Time zone	Address time zone

Change Request Types available:

CR Type	Description	Properties, Comments
IPA1S01	Create Personnel Area and activate	Create, 1-step
IPA1S02	Process Personnel Area and activate	Change, 1-step
IPA1SL1	Load Personnel Area and activate	Load, 1-step
IPA2S01	Create Personnel Area with approval	Create, 2-step
IPA2S02	Process Personnel Area with approval	Change, 2-step
IPA2SL1	Load Personnel Area with approval	Load, 2-step
IPA3S01	Create Personnel Area with proc. and appr	Create, 3-step
IPA3S02	Process Personnel Area with proc and appr	Change, 3-step

#### 4.2.3 Logistics

##### 4.2.3.1 BOM Usage

The Bill of Materials Usage is used to define the parts, components and raw materials needed, to produce a finished "end-item". The following attributes can be maintained:

Name	Description
BOM Usage	BOM Usage
Spare part indicator	Indicator: spare part
Spare part	Indicator: spare part
Production	Indicator: item relevant to production
Plant maintenance	Indicator: item relevant to plant maintenance
Costing	Indicator: item relevant to costing
Engineering/design	Indicator: item relevant to engineering
Sales	Indicator: item relevant to sales & distribution (SD)
HL configuration	Indicator: item relevant to high-level configuration
Relevant to sales	Indicator: item relevant to sales
Production relevant	Indicator: item relevant to production
Plant maintenance	Indicator: item relevant to plant maintenance
Relevancy to Costing Indicator	Indicator: item relevant to costing
Engineering/design	Indicator: item relevant to engineering
HL configuration	Indicator: high-level configuration
Description (medium text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IST1S01	Create BOM Usage and activate	Create, 1-step
IST1S02	Process BOM Usage and activate	Change, 1-step
IST1SL1	Load BOM Usage and activate	Load, 1-step
IST2S01	Create BOM Usage with approval	Create, 2-step
IST2S02	Process BOM Usage with approval	Change, 2-step
IST2SL1	Load BOM Usage with approval	Load, 2-step
IST3S01	Create BOM Usage with proc. and appr	Create, 3-step
IST3S02	Process BOM Usage with proc and appr	Change, 3-step

#### 4.2.3.2 Division

Divisions can be assigned to a Sales Division and Materials can be created referencing a Division. A Division consists out of multiple products or a product line with strong similarities. The following attributes can be maintained:

Attribute	Description
Divsion	Division
Description (short text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IPT1S01	Create Division and activate	Create, 1-step
IPT1S02	Process Division and activate	Change, 1-step
IPT1SL1	Load Division and activate	Load, 1-step
IPT2S01	Create Division with approval	Create, 2-step
IPT2S02	Process Division with approval	Change, 2-step
IPT2SL1	Load Division with approval	Load, 2-step
IPT3S01	Create Division with proc. and appr	Create, 3-step
IPT3S02	Process Division with proc and appr	Change, 3-step

#### 4.2.3.3 Factory Calendar

Factory Calendars are assigned to Plants. They are used to monitor & manage the working days and holidays in a year. The following attributes can be maintained:

Attribute	Description
Factory Calendar ID	Transport/Conversion: Identification (LIMU, TABU...)
Termination flag	Termination Flag
Curr. until year	Year, until which calendar is in buffer
Curr.from year	Year, from which calendar is in buffer
No.of first workday	Characteristic Basic Data
To Year	Year until which data is saved
Date	Creation date
Changed At	Calendar: Created or Changed At
User	Changed By
Bit for workday	Indicator: day is workday
Bit for workday	Indicator: day is workday
Bit for workday	Indicator: day is workday
Bit for workday	Indicator: day is workday
Holiday Calendar ID	Holiday Calendar ID
Termination flag	Interval Length for Leave Entitlement
Bit for workday	Indicator: day is workday

Bit for workday	Indicator: day is workday
Bit for workday	Indicator: day is workday
Bit for workday	Indicator: day is workday
Holidays long text	Language independent text
Description (long text)	Language dependent text
From year	Year from which data is stored
Year stored	Year for which levy is to be carried out
From date	Year from which levy is to be carried out
To date	To date
Bit for workday	Bit for workday
Text	Language Dependant Text
Language Key	Language Key

Change Request Types available:

CR Type	Description	Properties, Comments
IID1S01	Create Factory Calendar and activate	Create, 1-step
IID1S02	Process Factory Calendar and activate	Change, 1-step
IID1SL1	Load Factory Calendar and activate	Load, 1-step
IID2S01	Create Factory Calendar with approval	Create, 2-step
IID2S02	Process Factory Calendar with approval	Change, 2-step
IID2SL1	Load Factory Calendar with approval	Load, 2-step
IID3S01	Create Factory Calendar with proc. and appr	Create, 3-step
IID3S02	Process Factory Calendar with proc and appr	Change, 3-step

#### 4.2.3.4 Laboratory/Office

The Lab/Office object is used to define a Laboratory or Office at a certain location. They can be assigned to a Material (usually for chemicals). The following attributes can be maintained:

Attribute	Description
Lab/Office	Lab/Office
Description (medium text)	Language dependent Text

Change Request Types available:

CR Type	Description	Properties, Comments

---

ILB1S01	Create Lab/Office and activate	Create, 1-step
ILB1S02	Process Lab/Office and activate	Change, 1-step
ILB1SL1	Load Lab/Office and activate	Load, 1-step
ILB2S01	Create Lab/Office with approval	Create, 2-step
ILB2S02	Process Lab/Office with approval	Change, 2-step
ILB2SL1	Load Lab/Office with approval	Load, 2-step
ILB3S01	Create Lab/Office with proc. and appr	Create, 3-step
ILB3S02	Process Lab/Office with proc and appr	Change, 3-step

#### 4.2.3.5 Location

Locations form the foundation of transportation processes. They are used to define a place (physical or logical) in which resources are managed. The following attributes can be maintained:

Attribute	Description
Location	Location
Plant	Plant
Description (medium text)	Language dependant text
Address group	Address Group (Key) (Business Address Services)
City	City
c/o	Coname
House Number	House Number
Name	Language independent text
Name 2	Language independent text
Name 3	Language independent text
Name 4	Language independent text
Postal Code	City postal code
Description	Language dependent text
Search Term 1	Search Term 1
Search Term 2	Search Term 1
Street	Street
Title	Form-of-Address Key
Tax Jurisdiction	Tax Jurisdiction
Time zone	Address time zone
Country Key	Country Key
Region	Region

Change Request Types available:

CR Type	Description	Properties, Comments
ILC1S01	Create Location and activate	Create, 1-step
ILC1S02	Process Location and activate	Change, 1-step
ILC1SL1	Load Location and activate	Load, 1-step
ILC2S01	Create Location with approval	Create, 2-step
ILC2S02	Process Location with approval	Change, 2-step
ILC2SL1	Load Location with approval	Load, 2-step
ILC3S01	Create Location with proc. and appr	Create, 3-step
ILC3S02	Process Location with proc and appr	Change, 3-step

#### 4.2.3.6 *Material Group*

Material Groups are used to group materials with the same attributes or purpose. The following attributes (based on view V023 with tables T023 and T023T) can be maintained:

Attribute	Description
Material Group ID	Material Group
Description	Language dependent text
Valuation Classes	T025 - Valuation Classes
Division	TSPA - Organizational Unit: Sales Division
Default unit of weight	Unit of Measurement
Department	Department number
Class	Asset Class
AuthorizGroup	Authorization Group
Purch.value key	Purchasing Value Key
MG ref. matl	Material group reference material

Change Request Types available:

CR Type	Description	Properties, Comments
IMK1S01	Create Material Gr. and activate	Create, 1-step
IMK1S02	Process Material Gr. and activate	Change, 1-step
IMK1SL1	Load Material Gr. and activate	Load, 1-step
IMK2S01	Create Material Gr. with approval	Create, 2-step
IMK2S02	Process Material Gr. with approval	Change, 2-step

IMK2SL1	Load Material Gr. with approval	Load, 2-step
IMK3S01	Create Material Gr. with proc. and appr	Create, 3-step
IMK3S02	Process Material Gr. with proc and appr	Change, 3-step

#### 4.2.3.7 Material Status

A Material Status is used to indicate, if a Material is subject to any kind of restrictions (e.g. development, blocked, released). The following attributes can be maintained:

Name	Description
Material Status	Plant-Specific Material Status
Profile Name	Profile Name for ALE Change Authorization
Routing/master recipe message	Message if material is used in routing/master recipe
Inventory mgmt msg.	Message if material is used in Inventory Management
MRP message	Message if material is used in MRP
Purchasing msg.	Message if material is used in Purchasing
Mat. Cost Estimate Procedure	Material cost estimate procedure
POrder header msg.	Message if material is used in production order header
PO/network item msg.	Message if Material Used in Production Order or Network Item
PRT message	Message if PRT are assigned to routing or order
Plant maint. message	Message if material is used in Plant Maintenance
LT planning message	Message if material used in long-term planning
Distr. lock	Indicator: distribution lock
Ind. reqmt msg.	Message if independent requirement is created for material
Forecasting message	Message if material is used in Forecasting
QM inspection msg.	Message if material is used in QM inspection procedures
BOM header msg.	Message if Material Is Used in BOM Header
BOM item message	Message if material is used as BOM item
Transfer order message	Message if material is used in WM transfer order
Transfer requirement msg.	Message if material used in WM transfer reqmt/posting change
Blocked POrd. Gen.	Blocked for PO Generation in Purchase Quantity Planning
Lock Order Planning	Locked for Purchase Quantity Planning
Lock Rtn to Publ.	Locked for Return to Publisher
Blocked POrd. Gen.	Locked for Purchase Order Gen. for Return to Publisher
Description (medium text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IMS1S01	Create Material Status and activate	Create, 1-step
IMS1S02	Process Material Status and activate	Change, 1-step
IMS1SL1	Load Material Status and activate	Load, 1-step
IMS2S01	Create Material Status with approval	Create, 2-step
IMS2S02	Process Material Status with approval	Change, 2-step
IMS2SL1	Load Material Status with approval	Load, 2-step
IMS3S01	Create Material Status with proc. and appr	Create, 3-step
IMS3S02	Process Material Status with proc and appr	Change, 3-step

#### 4.2.3.8 Material Type

Material Types are used to categorize materials with similar attributes (e.g. finished products, raw materials, ...). The following attributes can be maintained:

Attribute	Description
Material Type	Material type
Valuation	Update Movements in Quantity in All Valuation Areas
Display material	Display material
Time till deleted	Time in days until a material is deleted
Valuation	Update Value Flows in All Valuation Areas
Authorization Group	Authorization Group
Ext. Purchase Orders	External Purchase Orders Allowed
Int. purchase orders	Internal purchase orders allowed
Class	Class
Class type	Class type
With Qty Structure	With qty structure
External no. assignment w/o check	External Number Assignment Without Validation
Field reference	Field selection reference
Initial Status	Initial status of a new batch
Acct cat. reference	Account category reference
Grouping indicator	Grouping indicator
Material is configurable	Configurable Material
Manufacturer part no.	Indicator: Use manufacturer part numbers
Pipeline mandatory	Pipeline Handling Mandatory
Material f. process	Material Master Record for a Process

Price ctrl mandatory	Price Control Mandatory
SRef: material type	Screen reference depending on the material type
X-plant matl status	Cross-Plant Material Status
Ref. material type	Reference material type
Print price	Print price
Maintenance status	Maintenance status
Description (medium text)	Language dependent text
Item category group	Default value for material item category group
Price control	Price control indicator
Material type ID	Material type ID
Valuation area	Valuation area
Pipeline mandatory	Pipeline Handling Mandatory
Quantity updating	Quantity Updating in Material Master Record
Value updating	Value Updating in Material Master Record
Pipeline allowed	Pipeline handling allowed
Maintenance status	Maintenance status of material master record

Change Request Types available:

CR Type	Description	Properties, Comments
IMT1S01	Create Material Type and activate	Create, 1-step
IMT1S02	Process Material Type and activate	Change, 1-step
IMT1SL1	Load Material Type and activate	Load, 1-step
IMT2S01	Create Material Type with approval	Create, 2-step
IMT2S02	Process Material Type with approval	Change, 2-step
IMT2SL1	Load Material Type with approval	Load, 2-step
IMT3S01	Create Material Type with proc. and appr	Create, 3-step
IMT3S02	Process Material Type with proc and appr	Change, 3-step

#### 4.2.3.9 MRP Area

MRP Area represents an organizational unit for which material requirements planning is carried out independently

Attribute	Description
BERTY	Type of MRP area
ORTZG	Receiving storage location
SPE_BNTYP	Business Types of MRP Area
WERZG	Plant

Change Request Types available:

CR Type	Description	Properties, Comments
IMRA1S01	Create MRP Area and activate	Create, 1-step
IMRA1S02	Process MRP Area and activate	Change, 1-step
IMRA1SL1	Load MRP Area and activate	Load, 1-step
IMRA2S01	Create MRP Area with Appr.	Create, 2-step
IMRA2S02	Process MRP Area with Appr.	Change, 2-step
IMRA2SL1	Load MRP Area with Appr.	Load, 2-step
IMRA3S01	Create MRP Area with proc. and appr.	Create, 3-step
IMRA3S02	Process MRP Area with proc. and appr.	Change, 3-step

#### 4.2.3.10 MRP Controller

An MRP Controller is a responsibility that designates who oversees material planning and ensures that stock, procurement, and demand are properly balanced. In business terms, it clarifies ownership for each material so planning tasks, exceptions, and decisions are consistently handled by the right person or team.

Attribute	Description
DISPO	MRP Controller
DSNAM	Name of MRP controller
DSTEL	MRP controller's telephone number
EKGRP	Purchasing Group
GSBER	Business Area
MEMPF	Recipient Name
PRCTR	Profit Center
USRKEY	Object ID for recipient
USRRTYP	Recipient type
WERKS	Plant

Change Request Types available:

CR Type	Description	Properties, Comments
IMRC1S01	Create MRP Controller and activate	Create, 1-step
IMRC1S02	Process MRP Controller and activate	Change, 1-step
IMRC1SL1	Load MRP Controller and activate	Load, 1-step
IMRC2S01	Create MRP Controller with appr.	Create, 2-step

---

IMRC2S02	Process MRP Controller with appr.	Change, 2-step
IMRC2SL1	Load MRP Controller with appr.	Load, 2-step
IMRC3S01	Create MRP Controller with proc. and appr	Create, 3-step
IMRC3S02	Process MRP Controller with proc. and app	Change, 3-step

#### 4.2.3.11 MRP Profile

A MRP Profile is used to define which fields are filled with which values when MRP data is entered in the material master record. It also defines which values can be overwritten.

Change Request Types available:

CR Type	Description	Properties, Comments
IMRP1S01	Create MRP Profile and activate	Create, 1-step
IMRP1S02	Process MRP Profile and activate	Change, 1-step
IMRP1SL1	Load MRP Profile and activate	Load, 1-step
IMRP2S01	Create MRP Profile with approval	Create, 2-step
IMRP2S02	Process MRP Profile with approval	Change, 2-step
IMRP2SL1	Load MRP Profile with approval	Load, 2-step
IMRP3S01	Create MRP Profile with proc. & app	Create, 3-step
IMRP3S02	Process MRP Profile with proc. & app	Change, 3-step

#### 4.2.3.12 MRP Type

MRP Types are used to control which procedure is used to plan a material and which MRP parameters can be entered when maintaining a material master record.

Attribute	Description
ALTS	Method for Selecting Alternative Bills of Material
AUFTL	Splitting Indicator
AUSS	Assembly scrap in percent
BESKZ	Procurement Type
BSTFE	Fixed lot size
BSTMA	Maximum Lot Size
BSTMI	Minimum Lot Size
BSTRF	Rounding value for purchase order quantity
DISGR	MRP Group

DISLS	Lot size (materials planning)
DISMM	MRP Type
DISPO	MRP controller
DZEIT	In-house production time
EISBE	Safety stock
EISLO	Minimum Safety Stock
EKGRP1	Purchasing group
FHORI	Scheduling Margin Key for Floats
FXHOR	Planning time fence
KAUSF	Component scrap in percent
KZBED	Indicator for Requirements Grouping
KZDIE	Indicator: MRP controller is buyer (deactivated)
KZECH	Determination of batch entry in the production/process order
LAGPR	Storage costs indicator
LFRHY	Planning cycle
LGFSB	Default storage location for external procurement
LGPRO	Issue Storage Location
LGRAD	Service level
LOSFX	Ordering costs
MAABC	ABC Indicator
MABST	Maximum stock level
MDACH	Action control: planned order processing
MEINS	Base Unit of Measure
MINBE	Reorder Point
MISKZ	Mixed MRP indicator
MRPPP	PPC planning calendar
MTVFP	Checking Group for Availability Check
PERIV1	Fiscal Year Variant
PERKZ	Period Indicator
PLIFZ	Planned delivery time in days
PLIFZX	Consider Planned Delivery Time of the MRP Area
RDPRF	Rounding Profile
RGEKZ	Indicator: Backflush
RWPRO	Range of coverage profile
SAUFT	Ind.: Repetitive mfg allowed
SBDKZ	Dependent requirements ind. for individual and coll. reqmts
SCHGT	Indicator: bulk material
SFEPR	Repetitive manufacturing profile
SHFLG	Safety time indicator (with or without safety time)
SHZET	Safety time (in workdays)

SOBSL	Special procurement type
STRGR	Planning strategy group
TAKZT	Takt time
USEQU	Quota arrangement usage
VINT1	Consumption period: backward
VINT2	Consumption period: forward
VPMAT	Planning material
VPREF	Conv. factor f. plng material
VPWRK	Planning plant
VRMOD	Consumption mode
WAERS1	Currency Key
WEBAZ	Goods receipt processing time in days
WZEIT	Total replenishment lead time (in workdays)

Additional Attributes available in the Data Model:

Attribute	Description
A1BED	Dependent reservation - standard orders
A2BED	Dependent reservation - plant maintenance orders and network
BBBED	Material staging reqmts (subcontr. reqmts) MRP element BB
CBPPT	Method by which a material is planned
DISVF	MRP procedure
DYFOL	Screen sequence for the header details
FXART	Firming Type of the Planning Result
ICBED	Reorder point planning with external requirements
KZMEB	Indicator: calculate reorder level
KZREG	Indicator: plan material regularly
KZSIB	Indicator: calculate safety stock
PROKZ	Forecast indicator
PROOS	MRP indicator of forecast
PROVB	Consumption indicator of forecast
PRRED	Reduce forecast requirements
RESPL	Indicator: delete firm planned orders
RYBED	Time-phased planning with requirements (MRP)
U1BED	Release for stock transfer order
U2BED	Delivery schedule for a stock transfer requisition
U4BED	Delivery schedule for stock transport scheduling agreement

Change Request Types available:

CR Type	Description	Properties, Comments
IMRT1S01	Create MRP Type	Create, 1-step
IMRT1S02	Process MRP Type	Change, 1-step
IMRT1SL1	Load MRP Type and activate	Load, 1-step
IMRT2S01	Create MRP Type with approval	Create, 2-step
IMRT2S02	Process MRP Type with approval	Change, 2-step
IMRT2SL1	Load MRP Type with approval	Load, 2-step
IMRT3S01	Create MRP Type with proc. & app	Create, 3-step
IMRT3S02	Process MRP Type with proc. & app	Change, 3-step

#### 4.2.3.13 Plant

Plants are used to divide a corporation according to production, procurement, maintenance, and materials planning and define a place where goods are produced, or services are provided. The following attributes can be maintained:

Attribute	Description
Plant ID	Plant
Name 1	Description 1
Name 2	Description 2
Language Key	Language
Street and House No.	Street and House Number
PO Box	PO Box
Postal Code	Postal Code
City	City
Country Key	Country Key
Region	Region Code
County code	County Code
City code	City Code
Jurisdiction code	Tax Jurisdiction
Factory calendar	Factory calendar key

Additional Attributes available in the Data Model:

Attribute Description
Variance Key
Activating requirements planning
Number of days for PO tolerance - Compress info records - SU

Valuation area
Sales district
Take regular vendor into account
Indicator: batch status management active
Superior Department Store
Batch Record: Type of DMS Used
Distribution profile at plant level
Order Allocation Run
Indicator: Season Active in Inventory Management
Division for intercompany billing
Maintenance Planning Plant
Business Place
Indicator: Conditions at plant level
Indicator: Source list requirement
Customer number of plant
Number of Days for First Reminder/Expediter
Number of Days for Second Reminder/Expediter
Number of Days for Third Reminder/Expediter
Vendor number of plant
Control of Credit of Cost Centers
Update of Activity Consumption in the Quantity Structure
Updating is active in actual costing
Updating is active for mixed costing
Node type: supply chain network
Structure for name formation
IPI credit allowed
Vendor type (refinery/mill/other) (Brazil)
Exchange valuation indicator
Cost Object Controlling linking active
Invoke Added-Function Source Determination via ATP
Store Category to Differentiate Store, Dep. Store, Shop
Tax Indicator: Plant (Purchasing)
Text name of 1st dunning of vendor declarations
Text name of the 2nd dunning of vendor declarations
Text name of 3rd dunning of vendor declarations
Sales organization for intercompany billing
Plant category
Shipping Point/Receiving Point
Rule for determining the sales area for stock transfers
Distribution channel for intercompany billing
SOP plant

Supply region (region supplied)
---------------------------------

Change Request Types available:

CR Type	Description	Properties, Comments
IPT1S01	Create Plant and activate	Create, 1-step
IPT1S02	Process Plant and activate	Change, 1-step
IPT1SL1	Load Plant and activate	Load, 1-step
IPT2S01	Create Plant with approval	Create, 2-step
IPT2S02	Process Plant with approval	Change, 2-step
IPT2SL1	Load Plant with approval	Load, 2-step
IPT3S01	Create Plant with proc. and appr	Create, 3-step
IPT3S02	Process Plant with proc and appr	Change, 3-step

#### 4.2.3.14 Storage Location

A Storage Location defines a location where physical goods are stored. While a Storage Location can have an own address, this address needs to be within a Plant, as all Storage Locations are a sub-Storage Location of a Plant. The following attributes can be maintained:

Attribute	Description
Storage location	Storage Location
Plant	Plant
SLoc MRP indicator	Storage location MRP indicator
Descr. of Storage Loc.	Description of Storage Location
Division	Division
Sales Organization	Sales Organization
Distribution Channel	Distribution Channel
Business System	Business System
Inv Mngmnt Type	Invoice management type
In-transit assignment	TD in-transit flag
License number	License number for untaxed stock
Description (short text)	Language dependent text
Shipping Point/Receiving Pt	Shipping Point/Receiving Point
Authorization check	Storage location authorization for goods movements active
Freeze book inv.SLoc	Freezing book inventory bal. allowed in stor. loc.
HU reqmnt	Handling unit requirement

Neg.stocks in SLoc.	Negative stocks allowed in storage location
Stor. resource	Storage location is allocated to resource (storage resource)
Sequence Number	Sequence Number
City	City
c/o	Coname
House Number	House Number
Name	Language independent text
Name 2	Language independent text
Name 3	Language independent text
Name 4	Language independent text
Postal Code	Postal Code
Description	Language dependent text
Search Term 1	Search Term 1
Search Term 2	Search Term 2
Street	Street
Title	Form-of-Address Key
Tax Jurisdiction	Tax Jurisdiction
Time zone	Address time zone
Country Key	Country Key
Region	Region

Change Request Types available:

CR Type	Description	Properties, Comments
ILG1S01	Create Storage Location and activate	Create, 1-step
ILG1S02	Process Storage Location and activate	Change, 1-step
ILG1SL1	Load Storage Location and activate	Load, 1-step
ILG2S01	Create Storage Location with approval	Create, 2-step
ILG2S02	Process Storage Location with approval	Change, 2-step
ILG2SL1	Load Storage Location with approval	Load, 2-step
ILG3S01	Create Storage Location with proc. and appr	Create, 3-step
ILG3S02	Process Storage Location with proc and appr	Change, 3-step

#### 4.2.3.15 Unit of Measurement

Units of Measurement are used to define quantities and physical units based on dimensions. The following attributes (based on table T006 and others) can be maintained:

Attribute	Description
Dimension	T006D - Dimensions
Unit of Measure	Internal Unit of Measurement Format
Measurement Unit Text	Language Dependent Text
Commercial / Techn. Text	Language dependent text
Decimal Places	Number of decimal places for number display
Float. Point Exp.	Base ten exponent for floating-point display
Numerator	Numerator for conversion to SI unit
Denominator	Denominator for conversion into SI unit
Exponent	base ten exponent for conversion to SI unit
Additive constant	Additive constant for conversion to SI unit
Decimal Rounding	No. of decimal places for rounding
Unit of meas.family:	Unit of measurement family
ISO code	ISO code for unit of measurement
Primary code	Selection field for conversion from ISO code to int. code
Commercial meas.unit:	Commercial measurement unit ID
Value-based commt:	Value-based commitment indicator

Change Request Types available:

CR Type	Description	Properties, Comments
IUM1S01	Create Unit of Meas. and activate	Create, 1-step
IUM1S02	Process Unit of Meas. and activate	Change, 1-step
IUM1SL1	Load Unit of Meas. and activate	Load, 1-step
IUM2S01	Create Unit of Meas. with approval	Create, 2-step
IUM2S02	Process Unit of Meas. with approval	Change, 2-step
IUM2SL1	Load Unit of Meas. with approval	Load, 2-step
IUM3S01	Create Unit of Meas. with proc and appr	Create, 3-step
IUM3S02	Process Unit of Meas with proc and appr	Change, 3-step

#### 4.2.3.16 Classification: CClass

The classification is a general concept which for example allows business users to define additional attributes (characteristics) which can be used as additional attributes in the maintenance of material data. It consists of characteristics which are bundled in classes.

Attributes for characteristics available:

<b>Attribute</b>	<b>Description</b>
ABTEI	Organizational Area
AENNR	Change Number
AMERK	Relevancy indicator (print, search, display)
ANZRE	Display Relevant
BLLIN	Line Number in Block
CKBOX	Checkbox
COLOR	Color
CUSTR	Text, 40 Characters Long
DATUV	Valid-From Date
DINKB	Code letter
DPLEN	Field output length
DPTXT	Display Text Instead of Content
DRURE	Print Relevant
HERKU	Characteristic origin
IMERK	Internal characteristic
INDRE	Index Characteristic
INPUT	Entry
INTSF	Highlighted
INVER	Inverse
JUSTR	Display right-justified
LKENZ	Deletion Indicator
MKENN	Standard Code Letter
OFFST	Offset in work area
OMERK	Object-Dependent Characteristic
RELEV	Relevancy Indicator
SELRE	Search Relevant
TECHV	Indicator: changed with new effectivity
VMERK	New characteristic without values

Class attributes available:

<b>Attribute</b>	<b>Description</b>
ADATU	Date on which the record was created
AENNR1	Change Number
ANAME	Name of Person who Created the Object
ANZUO	Number of Assignments
AUSGD	Issue date
BGRKL	Classification authorization group
BGRKP	Class maintenance authorization group

---

BGRSE	Authorization group for finding objects
BISDT	Valid-to date
BNAME	Block name
CLALT	Alternative Display Format
CLASS1	Class
CLMOD	Default Class Data - Can Be Overwritten in Component
CLMUL	Multiple Selection Allowed
CLOBK	Required Component
CVIEW	Organizational Area
DINKZ	DIN class indicator
DISST	Low-Level Code
DOKAR	Document Type
DOKTL	Document part
DOKVR	Document version
GENRKZ	Table for Finding Objects: To Be Generated=X, Generated=R
KATALOG	Name of External Catalog
KDOKAZ	Always Display Document for Class
KLAGR	Class Group
KLART	Class Type
KNOBJ	Number of Object with Assigned Dependencies
LBREI	Total width of list
LEIST	Characteristics table
LOCLA	Local class

Change Request Types for Characteristics available:

<b>CR Type</b>	<b>Description</b>	<b>Properties, Comments</b>
ICH1S01	Create Characteristic and activate	Create, 1-step
ICH1S02	Process Characteristic and activate	Change, 1-step
ICH1SL1	Load Characteristic and activate	Load, 1-step
ICH2S01	Create Characteristic with approval	Create, 2-step
ICH2S02	Process Characteristic with approval	Change, 2-step
ICH2SL1	Load Characteristic with approval	Load, 2-step
ICH3S01	Create Characterist with proc. and appr.	Create, 3-step
ICH3S02	Process Characteris with proc. and appr.	Change, 3-step

Change Request Types for Classes available:

<b>CR Type</b>	<b>Description</b>	<b>Properties, Comments</b>

ICL1S01	Create Class and activate	Create, 1-step
ICL1S02	Process Class and activate	Change, 1-step
ICL1SL1	Load Class and activate	Load, 1-step
ICL2S01	Create Class with approval	Create, 2-step
ICL2S02	Process Class with approval	Change, 2-step
ICL2SL1	Load Class with approval	Load, 2-step
ICL3S01	Create Class with proc. and appr.	Create, 3-step
ICL3S02	Process Class with proc. and appr.	Change, 3-step

#### 4.2.4 Sales

##### 4.2.4.1 *Product Hierarchy*

A Product Hierarchy defines a structure of products or materials which can be used for statistical analysis or pricing. Different levels can be defined (e.g., Branches and Divisions) and used for the creation of the structure.

New Nodes can be created and maintained in different languages and are assigned into the Product Hierarchy structure before they are replicated to a target system. SAP receivers store that data in table T179.

During the initial load of a product hierarchy, external numbers defined in the source system are loaded and mapped to RDM numbers. New Nodes will get new RDM numbers (through number ranges defined for each product hierarchy level) and external numbers.

Assignments of Nodes to the Product Hierarchy can be changed and might include the new assignment of a complete subtree consisting of multiple Nodes. This will change external numbers accordingly for usage in receiver systems.

The following attributes can be maintained:

Attribute	Description
Product Hierarchy Name	Product Hierarchy Name
External Number	External number
Description (Long Text)	Language dependent text
Product Hierarchy Node	Product Hierarchy Node
Prod.Hier. Level	Product Hierarchy Level

Optional:

Product Hierarchy Sub Node	Product Hierarchy Sub Node
----------------------------	----------------------------

Change Request Types:

CR Type	Description	Properties, Comments
IPH1SE1	Create Prod.Hier. and activate	Create, 1-step
IPH1SE2	Process Prod.Hier. and activate	Change, 1-step
IPH1SE4	Hierarchy Proc. Prod. Hier. w Activate	Load, 1-step
IPH1SEL	Load Prod.Hier. and activate	Load, 1-step
IPH2SE1	Create Prod.Hier. with approval	Create, 2-step
IPH2SE2	Process Prod.Hier. with approval	Change, 2-step
IPH2SE4	Hierarchy Proc. Prod. Hier. with Approv.	Load, 2-step
IPH2SEL	Load Prod.Hier. with approval	Load, 2-step
IPH3SE1	Create Prod.Hier. with proc. and appr.	Create, 3-step
IPH3SE2	Process Prod.Hier. with proc. and appr.	Change, 3-step

#### 4.2.4.2 Sales Organization

Sales Organizations are used to define responsibilities for selling materials and services. The following attributes can be maintained:

Attribute	Description
Sales Organization ID	Sales Organization
Description	Language dependent text
Currency	Currency Code
Address text name	Text name for form text module short address
Letter header text	Text name for form text module letter header
Footer lines text	Text name for formula text module footer lines
Greeting text name	Text name for form text module: Greeting
Text SDS sender	Text names for layout-set module SDS sender
Ref. Sales Organization	Reference sales org.for sales doc.types (by sales area)
Cust.inter-co.bill.	Customer number for intercompany billing
Sales org.calendar	Sales organization calendar
Rebate proc.active	Rebate processing active in the sales organization
Purch. Organization	Purchasing Organization
Purchasing Group	Purchasing Group
Vendor	Account Number of Vendor or Creditor
Order Type	Order Type (Purchasing)
Plant	Plant
Storage location	Storage location

Movement Type	Movement Type (Inventory Management)
---------------	--------------------------------------

Additional Attributes available in the Data Model:

Attribute Description
Purchasing document category
Time of numbering for deliveries
Maximum Number of Items in Billing Document
Tax code for SD documents
Price protection period
Unit for price protection
Determining the VAT registration number

Change Request Types available:

CR Type	Description	Properties, Comments
ISO1S01	Create Sales Org. and activate	Create, 1-step
ISO1S02	Process Sales Org. and activate	Change, 1-step
ISO1SL1	Load Sales Org. and activate	Load, 1-step
ISO2S01	Create Sales Org. with approval	Create, 2-step
ISO2S02	Process Sales Org. with approval	Change, 2-step
ISO2SL1	Load Sales Org. with approval	Load, 2-step
ISO3S01	Create Sales Org. with proc. and appr	Create, 3-step
ISO3S02	Process Sales Org. with proc and appr	Change, 3-step

#### 4.2.4.3 Payment Terms

Payment Terms are used to define the terms of payment used for customers and vendors based on the date of payment (e.g. 3% discount within 14 days). The following attributes can be maintained:

Attribute	Description
Payment Term ID	Payment Term
Sales Text	Payment Term Description (Text)
Day Limit	Day Limit
Own Explanation	Own Explanation (Text)
Customer	Indicator: Customer account type

Vendor	Indicator: Vendor account type
Fixed Day	Fixed Day
Additional Months	Additional Months
Block Key	Transfer payment block when changing terms of payment?
Payment Method	Transfer payment method when changing terms of payment?
Default for Baseline date	Indicator: No default for the base date / Propose document date / Propose entry date / Propose posting date
Installment Payment	Indicator: Term for installment payment
Rec. Entries Suppl. In Master	Recurring Entries: Add Terms of Payment from Master Record
Percentage – Term 1	Cash Discount Percentage Rate
No of days – Term 1	Days from Baseline Date for Payment
Fixed Date – Term 1	Due Date for Special Condition
Add. Months – Term 1	Additional Months for Special Condition (Term 1)
Percentage – Term 2	Cash Discount Percentage Rate
No of days – Term 2	Days from Baseline Date for Payment
Fixed Date – Term 2	Due Date for Special Condition
Add. Months – Term 2	Additional Months for Special Condition (Term 2)
No of days – Term 3	Days from Baseline Date for Payment
Fixed Date – Term 3	Due Date for Special Condition
Add. Months – Term 3	Additional Months for Special Condition (Term 3)
Explanation 1	Explanation Term 1 (Text)
Explanation 2	Explanation Term 2 (Text)
Explanation 3	Explanation Term 3 (Text)
Explanation 4	Explanation 4

Change Request Types available:

CR Type	Description	Properties, Comments
IPY1S01	Create Payment Term and activate	Create, 1-step
IPY1S02	Process Payment Term and activate	Change, 1-step
IPY1SL1	Load Payment Term and activate	Load, 1-step
IPY2S01	Create Payment Term with approval	Create, 2-step
IPY2S02	Process Payment Term with approval	Change, 2-step
IPY2SL1	Load Payment Term with approval	Load, 2-step
IPY3S01	Create Payment Term with proc. and appr	Create, 3-step
IPY3S02	Process Payment Term with proc and appr	Change, 3-step

#### 4.2.4.4 *Distribution Channel*

Distribution Channels are assigned to at least one Sales Organization. They define the channel through which goods (or e.g. services) reach a customer. The following attributes can be maintained:

Attribute	Description
Distribution Channel	Distribution Channel
Description (Short Text)	Language dependent Text

Change Requests Types available:

CR Type	Description	Properties, Comments
IVT1S01	Create Distribution Channel and activate	Create, 1-step
IVT1S02	Process Distribution Channel and activate	Change, 1-step
IVT1SL1	Load Distribution Channel and activate	Load, 1-step
IVT2S01	Create Distribution Channel with approval	Create, 2-step
IVT2S02	Process Distribution Channel with approval	Change, 2-step
IVT2SL1	Load Distribution Channel with approval	Load, 2-step
IVT3S01	Create Distribution Channel with proc. and appr	Create, 3-step
IVT3S02	Process Distribution Channel with proc and appr	Change, 3-step

#### 4.2.4.5 *Incoterms*

Incoterms are used to define internationally recognized trading terms. These terms are approved by the International Chamber of Commerce (ICC). The following attributes can be maintained:

Attribute	Description
Incoterms	Incoterms (Part 1)
GI at loading/proof of delivery	Goods issue at loading, proof of delivery (POD)
Title transf. loc.	Title transfer loc.
Location mandatory	Location is mandatory
Description (medium text)	Language dependent Text

Change Requests Types available:

CR Type	Description	Properties, Comments
IIC1S01	Create Incoterm and activate	Create, 1-step
IIC1S02	Process Incoterm and activate	Change, 1-step
IIC1SL1	Load Incoterm and activate	Load, 1-step
IIC2S01	Create Incoterm with approval	Create, 2-step
IIC2S02	Process Incoterm with approval	Change, 2-step
IIC2SL1	Load Incoterm with approval	Load, 2-step
IIC3S01	Create Incoterm with proc. and appr	Create, 3-step
IIC3S02	Process Incoterm with proc and appr	Change, 3-step

#### 4.2.4.6 Sales Group

Sales Groups are used to define groups of sales persons working for a certain company or department. This primarily helps to monitor and manage work force. The following attributes can be maintained:

Attribute	Description
Sales Group	Sales group
Description (short text)	Language dependent Text

Change Requests Types available:

CR Type	Description	Properties, Comments
IVK1S01	Create Sales Group and activate	Create, 1-step
IVK1S02	Process Sales Group and activate	Change, 1-step
IVK1SL1	Load Sales Group and activate	Load, 1-step
IVK2S01	Create Sales Group with approval	Create, 2-step
IVK2S02	Process Sales Group with approval	Change, 2-step
IVK2SL1	Load Sales Group with approval	Load, 2-step
IVK3S01	Create Sales Group with proc. and appr	Create, 3-step
IVK3S02	Process Sales Group with proc and appr	Change, 3-step

#### 4.2.4.7 Shipping Conditions

Shipping Conditions are assigned to a customer and define the conditions, under which a shipment to said customer takes place. They are crucial for determining the Shipping Point of a delivery. The following attributes can be maintained:

Attribute	Description
Shipping Conditions	Shipping Conditions
Description (short text)	Language dependent Text

Change Requests Types available:

CR Type	Description	Properties, Comments
IVB1S01	Create Shipping Condition and activate	Create, 1-step
IVB1S02	Process Shipping Condition and activate	Change, 1-step
IVB1SL1	Load Shipping Condition and activate	Load, 1-step
IVB2S01	Create Shipping Condition with approval	Create, 2-step
IVB2S02	Process Shipping Condition with approval	Change, 2-step
IVB2SL1	Load Shipping Condition with approval	Load, 2-step
IVB3S01	Create Shipping Condition with proc. and appr	Create, 3-step
IVB3S02	Process Shipping Condition with proc and appr	Change, 3-step

#### 4.2.4.8 *Shipping Point*

A physical location in the company from which goods are prepared and dispatched. It is the operational unit responsible for picking, packing, loading, and shipping customer orders.

Attribute	Description
ADRNR	Address
VSTEL	Shipping Point / Receiving Point
NACHA	Message transmission medium
VSZTP	Dispatch time
LAZBS	Determine loading time
RIZBS	Determine pick/pack time
KOQUI	Subject to Pick Confirmation
IMESS	Display information messages in collective processing log
AUTOMATIC_PICK	Enable Automatic Picking in Delivery
ANZAL	Number of messages (original + copies)
KOMSU	Picking subsystem
LOADTG	Gross loading time (ignoring work times)
PIPATG	Pick/pack time in workdays
LOADTN	Loading time in working hours
PIPATN	Pick/pack time in work hours

VTRZT	Rounding-up period for delivery scheduling (in days)
TXNAM_ADR	Text name for form text module short address
TXNAM_KOP	Text name for form text module letter header
TXNAM_FUS	Text name for formula text module footer lines
TXNAM_GRU	Text name for form text module: Greeting
TXNAM_SDB	Text names for layout-set module SDS sender
SPRAS	Message language
KSCHL	Output Type
ALAND	Departure country (country from which the goods are sent)
FABKL	Factory calendar key
AZONE	Departure Zone
TSTRID	Working time from sales view
VTEXT	Description
SPRAS	Language Key
VSTEL	Shipping Point / Receiving Point

Change Requests Types available:

CR Type	Description	Properties, Comments
IVL1S01	Create Shipping Point and activate	Create, 1-step
IVL1S02	Process Shipping Point and activate	Change, 1-step
IVL1SL1	Load Shipping Point and activate	Load, 1-step
IVL2S01	Create Shipping Point with approval	Create, 2-step
IVL2S02	Process Shipping Point with approval	Change, 2-step
IVL2SL1	Load Shipping Point with approval	Load, 2-step
IVL3S01	Create Shipping Point with proc. and app	Create, 3-step
IVL3S02	Process Shipping Point with proc. and ap	Change, 3-step

#### 4.2.4.9 *Shipping Type*

Shipping Types are used to define the transportation method, that goods are delivered with (e.g. Rail, Road, ...). The following attributes can be maintained:

Attribute	Description
Shipping Type	Shipping type
Description (short text)	Language dependent Text
Mode of Transport	Mode of transport
Ship. Type proc. grp	Shipping type procedure group

Change Requests Types available:

CR Type	Description	Properties, Comments
IVS1S01	Create Shipping Type and activate	Create, 1-step
IVS1S02	Process Shipping Type and activate	Change, 1-step
IVS1SL1	Load Shipping Type and activate	Load, 1-step
IVS2S01	Create Shipping Type with approval	Create, 2-step
IVS2S02	Process Shipping Type with approval	Change, 2-step
IVS2SL1	Load Shipping Type with approval	Load, 2-step
IVS3S01	Create Shipping Type with proc. and appr	Create, 3-step
IVS3S02	Process Shipping Type with proc and appr	Change, 3-step

## 4.2.5 Purchasing

### 4.2.5.1 Purchasing Group

Purchasing Groups define individuals or groups of individuals which are responsible for specific operational areas. The following attributes (based on view V\_024 with table T024) can be maintained:

Attribute	Description
Purchasing Grp	Purchasing Group
Description	Language independent text
Tel. Purchasing Group	Telephone number of purchasing group (buyer group)
Tel. Dialing Code + Number	Telephone no.: dialling code+number
Tel. Extension	Telephone no.: Extension
E-Mail Address	E-Mail Address
Fax Purchasing Group	Fax number of purchasing (buyer) group

Change Request Types:

CR Type	Description	Properties, Comments
IEG1S01	Create Purch.Gr. and activate	Create, 1-step
IEG1S02	Process Purch.Gr. and activate	Change, 1-step
IEG1SL1	Load Purch.Gr. and activate	Load, 1-step
IEG2S01	Create Purch.Gr. with approval	Create, 2-step
IEG2S02	Process Purch.Gr. with approval	Change, 2-step
IEG2SL1	Load Purch.Gr. with approval	Load, 2-step
IEG3S01	Create Purch.Gr. with proc. and appr.	Create, 3-step
IEG3S02	Process Purch.Gr. with proc. and appr.	Change, 2-step

#### 4.2.5.2 Purchasing Organization

A Purchasing Organization is responsible for all purchasing activities and can be divided in several purchasing groups. The following attributes (based on view V\_T024E with table T024E) can be maintained:

Attribute	Description
Purch. Organization	Purchasing Organization
Description	Language independent text
Company Code	Assignment of Purchasing Organization to Company Code

Change Request Types available:

CR Type	Description	Properties, Comments
IEO1S01	Create Purch.Org. and activate	Create, 1-step
IEO1S02	Process Purch.Org. and activate	Change, 1-step
IEO1SL1	Load Purch.Org. and activate	Load, 1-step
IEO2S01	Create Purch.Org. with approval	Create, 2-step
IEO2S02	Process Purch.Org. with approval	Change, 2-step
IEO2SL1	Load Purch.Org. with approval	Load, 2-step
IEO3S01	Create Purch.Org. with proc. and appr.	Create, 3-step
IEO3S02	Process Purch.Org. with proc. and appr.	Change, 2-step

## 4.2.6 General Settings

### 4.2.6.1 *Country*

Countries are used to define country specific attributes like currencies, decimal formats or postal codes. The following attributes (based on view V\_T005 with tables T005, T005T, T002, T002T and T005X) can be maintained:

Attribute	Description
Ctry Key	Country Key
Name	Language dependent text
Long name	Language dependent text
Nationality	Language dependent text
Nationality (Long)	Language dependent text
Veh. country key	Vehicle country key
Index-based curr.	Currency Key of the Index-Based Currency
Language Key	Language Key
Hard currency	Currency Key of the Hard Currency
ISO code	Country ISO code
ISO code 3 char	ISO country code 3 char
ISO Code Numeric 3-Chars	ISO Country Code Numeric 3-Characters
Procedure	Procedure (Pricing, Output Control, Acct. Det., Costing,...)
Trde stat.short name	Short Name for Foreign Trade Statistics
Intrastat code	Intrastat Code
EU Member	Indicator: European Union Member?
Net Discount Base	Indicator: Discount base amount is the net value
Capital Goods Ind	Indicator: Display Capital Goods Indicator?
Net Tax base	Indicator: Base amount for tax is net of discount ?
Decimal Format	Decimal Format
Date format	Date format
Postal code required	Flag: Street address postal code required entry?
PO Box postal code	Flag: PO Box postal code required?
Postal code length	Postal code length (max)
City file active	Flag: City file address check
Street postcode	Flag: Street-specific postal code? (City file)
Check rule for postal code	Rule for the postal code field check
Address layout key	Formatting routine key for printing addresses
Print Country Name	Flag: Print country name in foreign addresses?

Change Request Types available:

CR Type	Description	Properties, Comments
ILA1S01	Create Country and activate	Create, 1-step
ILA1S02	Process Country and activate	Change, 1-step
ILA1SL1	Load Country and activate	Load, 1-step
ILA2S01	Create Country with approval	Create, 2-step
ILA2S02	Process Country with approval	Change, 2-step
ILA2SL1	Load Country with approval	Load, 2-step
ILA3S01	Create Country with proc. and appr.	Create, 3-step
ILA3S02	Process Country with proc. and appr.	Change, 2-step

#### 4.2.6.2 Region

Regions are assigned to countries and have different meanings in the countries. Examples: province, federal state, department or state. The following attributes (based on view V\_T005S with tables T005S and T005U) can be maintained:

Attribute	Description
Ctry Key	Country Key
Region	Region (State, Province, County)
Description	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
IRE1S01	Create Region and activate	Create, 1-step
IRE1S02	Process Region and activate	Change, 1-step
IRE1SL1	Load Region and activate	Load, 1-step
IRE2S01	Create Region with approval	Create, 2-step
IRE2S02	Process Region with approval	Change, 2-step
IRE2SL1	Load Region with approval	Load, 2-step
IRE3S01	Create Region with proc. and appr.	Create, 3-step
IRE3S02	Process Region with proc. and appr.	Change, 2-step

#### 4.2.6.3 Language Key

Language Keys are used for defining the language in which you enter texts, display texts and print documents. The following attributes can be maintained:

Attribute	Description
Language Key	Language Key
Degree of Translation of Lang.	Degree of Translation of Language
Lang. (ISO 639)	2-Character SAP Language Code
Language specifications	Language specifications
Description (short text)	Language dependent text

Change Request Types available:

CR Type	Description	Properties, Comments
ILU1S01	Create Language Key and activate	Create, 1-step
ILU1S02	Process Language Key and activate	Change, 1-step
ILU1SL1	Load Language Key and activate	Load, 1-step
ILU2S01	Create Language Key with approval	Create, 2-step
ILU2S02	Process Language Key with approval	Change, 2-step
ILU2SL1	Load Language Key with approval	Load, 2-step
ILU3S01	Create Language Key with proc. and appr	Create, 3-step
ILU3S02	Process Language Key with proc and appr	Change, 3-step

#### 4.2.6.4 Public Holiday

Public Holidays are used for time management functionalities in SAP and define fixed-date holidays (like New Year), moveable holidays (e.g. easter based) and holiday rules (like "next Monday" if "Sunday"). They are assigned to Holiday Calendars. The following attributes can be maintained:

Attribute	Description
Holiday Type	Public holiday key
Month	Month for holiday calculation
Sort Criterion	Sort field for public holidays
Day	Day of month for public holiday calculation
Distance from Easter	Distance of public holiday from Easter
Holiday class	Holiday class

Holiday Rule	Holiday rule
Guaranteed	Public holiday guaranteed flag
Day	Day for public holiday calculation
Religion	Calendar religion key
Short Holiday Name	Short Holiday Description
Long Holiday Name	Short Holiday Description

Change Request Types available:

CR Type	Description	Properties, Comments
IFT1S01	Create Public Holiday and activate	Create, 1-step
IFT1S02	Process Public Holiday and activate	Change, 1-step
IFT1SL1	Load Public Holiday and activate	Load, 1-step
IFT2S01	Create Public Holiday with approval	Create, 2-step
IFT2S02	Process Public Holiday with approval	Change, 2-step
IFT2SL1	Load Public Holiday with approval	Load, 2-step
IFT3S01	Create Public Holiday with proc. and appr	Create, 3-step
IFT3S02	Process Public Holiday with proc and appr	Change, 3-step

#### 4.2.6.5 Holiday Calendar

Holiday Calendars are used to manage “working” and “non-working” days based on a region or country, a validity period and a list of public holidays. The following attributes can be maintained:

Attribute	Description
Holiday Calendar ID	Public Holiday Calendar
From Year	Year stored from
To Year	Year stored to
Public Holiday	Public Holidays assigned

Change Request Types available:

CR Type	Description	Properties, Comments
IHI1S01	Create Holiday Calendar and activate	Create, 1-step
IHI1S02	Process Holiday Calendar and activate	Change, 1-step
IHI1SL1	Load Holiday Calendar and activate	Load, 1-step

---

IHI2S01	Create Holiday Calendar with approval	Create, 2-step
IHI2S02	Process Holiday Calendar with approval	Change, 2-step
IHI2SL1	Load Holiday Calendar with approval	Load, 2-step
IHI3S01	Create Holiday Calendar with proc. and appr	Create, 3-step
IHI3S02	Process Holiday Calendar with proc and appr	Change, 3-step